

Package ‘adea’

September 7, 2021

Type Package

Depends Benchmarking, combinat, lpSolveAPI, methods, R (>= 3.5.0),
rmarkdown

Imports knitr

VignetteBuilder knitr

Version 1.1.6

Date 2021-09-02

ByteCompile true

Title Alternate DEA Package

Maintainer Manuel Munoz-Marquez <manuel.munoz@uca.es>

Description The meaning of adea is “alternate DEA”. This package is devoted to provide the alternative method of DEA described in the paper entitled “Stepwise Selection of Variables in DEA Using Contribution Load”, by F. Fernandez-Palacin, M. A. Lopez-Sanchez and M. Munoz-Marquez. *Pesquisa Operacional* 38 (1), pg. 1-24, 2018. <[doi:10.1590/0101-7438.2018.038.01.0031](https://doi.org/10.1590/0101-7438.2018.038.01.0031)>.

A full functional on-line and interactive version is available at
<<https://knuth.uca.es/shiny/DEA/>>.

License GPL (>= 3)

RoxygenNote 7.1.1

NeedsCompilation no

Author Fernando Fernandez-Palacin [aut]
(<<https://orcid.org/0000-0002-3525-2924>>),
Manuel Munoz-Marquez [aut, cre]
(<<https://orcid.org/0000-0003-4157-8784>>)

Repository CRAN

Repository/R-Forge/Project adea

Repository/R-Forge/Revision 11

Repository/R-Forge/DateTimeStamp 2021-09-03 16:09:09

Date/Publication 2021-09-07 09:40:05 UTC

R topics documented:

adea-package	2
adea	4
adea_hierarchical	6
adea_loads	8
adea_load_leverage	9
adea_parametric	10
adea_stepwise	12
cadea	13
cardealers1	15
cardealers2	16
cardealers3	17
cardealers4	18
print.adea	18
print.adeahierarchical	19
print.adealoadleverage	19
print.adeaparametric	20
print.adeastepwise	20
print.cadea	21
spanishuniversities2018	21
summary.adea	22
summary.adeahierarchical	23
summary.adeaparametric	23
summary.adeastepwise	24
summary.cadea	24
tokyo_libraries	25
Index	26

adea-package	<i>Data Envelopment Analysis: Variable Selection, Constrained ADEA and Leverage Units</i>
--------------	---

Description

Package: adea

Version: 1.1.6

Date: 2021-09-02

License: GPL (>= 3)

DEA, that means Data Envelopment Analysis, consider a set of DMUs (Decision Making Units) and computes an efficiency score for each DMU. Such score is defined as a weighted ratio between several inputs and outputs values for such DMU.

This package provides an implementation of the ADEA method for variable selection in DEA. ADEA methodology includes a new phase in the classical DEA analysis that measures the relative importance of each input and output variable. This above-mentioned measure is called load ratio or contribution. A load for the whole model is also defined. Using such measure, a procedure to select an optimised or relevant set of variables has been developed.

A variable load is a number between 0 and 1. Where 0 means that the contribution of that variable to the efficiency values is negligible. In an ideal case, each input or output variable will have a load of 1.

As it is usually done in DEA, these loads are computed as its maximum allowable value. Using alternative sets of weights, this procedure don't change efficiency scores. But because the sum of all of them is 1, when one variable increases its load, any other decrease in value. So only the lowest value of all loads has a real meaning. This lowest value can be taken as a significance measure of the entire model.

This measure, load, has two important properties that easy its interpretation:

- It has a bounded range from 0 to the number of input or output, and 1 as its ideal value.
- It is invariant by changes of scale.

ADEA analysis can be done measuring only input variables, in this case ADEA analysis has input load. `orientation`. output when only output variables are considered. And `inoutput load. orientation` when all variables in the model are taken into account.

The package is named after its main function. `adea` makes a DEA analysis using alternative optimal solution of the same programs that DEA uses to compute efficiency scores. For a detailed description of the maths behind the model, see the references.

The main functions that this package provides are:

- `adea`: It makes ADEA analysis giving, efficiency scores for each DMU, a set of weight, and a load for each input and output variable, and also model load.
- `cadea`: Constrained ADEA analysis to force that variable loads fall in a given range. The efficiencies scores will change in order to allow this.
- `adea_load_average`: Search for DMU's with higher impact on ADEA model.

Note

The package is ready for translations, so contributions with translated versions of po files will be very welcomed.

Author(s)

Fernando Fernandez-Palacin <fernando.fernandez@uca.es> and Manuel Munoz-Marquez <manuel.munoz@uca.es>
Mantainer: Manuel Munoz-Marquez <manuel.munoz@uca.es>

References

Stepwise Selection of Variables in DEA Using Contribution Load. *F. Fernandez-Palacin, M. A. Lopez-Sanchez and M. Munoz-Marquez*. *Pesquisa Operacional* 38 (1), pg. 1-24, 2018. <DOI:10.1590/0101-7438.2018.038.01.0000>.

Methodology for calculating critical values of relevance measures in variable selection methods in data envelopment analysis. *Jeyms Villanueva-Cantillo* and *Manuel Munoz-Marquez*. *European Journal of Operational Research*, 290 (2), pg. 657-670, 2021. <DOI:10.1016/j.ejor.2020.08.021>.

adea

ADEA analysis to variable selection in DEA

Description

ADEA analysis, computes a score for each DMU and load ratio for each variable.

Usage

```
adea(
  input,
  output,
  orientation = c("input", "output"),
  load.orientation = c("inoutput", "input", "output"),
  name = "",
  eff.tolerance = 0.001
)
```

Arguments

input	A matrix or a data frame with the inputs of units to be evaluated, one row for each DMU and one column for each input.
output	A matrix or a data frame with the outputs of units to be evaluated, one row for each DMU and one column for each output.
orientation	Use "input" for input orientation or use "output" for output orientation in DEA model.
load.orientation	It allows the selection of variables to be included in load analysis. Its default value is "inoutput" which means that all input and all output variables will be included. Use "input" or "output" to include only input or output variables in load analysis.
name	An optional descriptive name for the model. It will be shown in print and summary results.
eff.tolerance	A value between 0 and 1 to tolerance when considering a DMU as efficient in reports.

Details

This function computes an efficiency score for each DMU, the same as in standard DEA model. Then a load ratio for each variable is computed searching two new set of weights while keeping DMU's scores.

The load ratio of a variable is a number between 0 and 1. Where 0 means that the contribution of that variable to the efficiency computations is negligible. In an ideal case, each input or output variable will have a load of 1 divide by the number of them.

As it is usually done in DEA this load ratio has been computed as its maximum allowable value. But because the sum of all of them is 1, when one increases its load ratio any other decreases its value. So only the lowest value of all load ratios, this is load model, has a real meaning. This lowest value can be taken as a significance measure of the entire model.

Value

The function return an adea class object with the following named members:

- `eff` is a vector with DMU's scores
- `neff` is the number of efficient DMU with `eff.tolerance`. It means DMUs with efficiencies between $1 - \text{eff.tolerance}$ and $1 + \text{eff.tolerance}$.
- `load.orientation` is the load orientation, one of 'input', 'output' or 'inoutput'. The last is the default value.
- `name`: A label of the model
- `orientation`: DEA model orientation 'input' or 'output'
- `ux`: A set of weights for inputs
- `vy`: A set of weights for output
- `load`: A list with all information about loads:
 - `ratios$input`: A vector with load ratios of input variables
 - `ratios$output`: A vector with load ratios of output variables
 - `load`: The lowest load ratio, which is the load of the ADEA model
 - `lp`: A pointer to the linear programming program of the model. Mainly for research purpose
 - `iinput`: A vector of index of inputs that almost reach the load level
 - `ioutput`: A vector of index of outputs that almost reach the load level

See Also

[adea-package](#).

Examples

```
data('cardealers4')
input <- cardealers4[, 1:2]
output <- cardealers4[, 3:4]

# Compute adea model
model <- adea(input, output)
model
# Dealer A Dealer B Dealer C Dealer D Dealer E Dealer F
# 0.9915929 1.0000000 0.8928571 0.8653846 1.0000000 0.6515044

# Get model's load
```

```

model$load$load
# [1] 0.6666667

# Get model's load ratios
model$load$ratios
# $input
# Employees Depreciation
# 0.6666667 1.3333333
# $output
# CarsSold WorkOrders
# 1.2663476 0.7336524

```

adea_hierarchical *Selection of an optimal subset of variables for DEA analysis*

Description

The function returns a list of DEA models dropping one variable in each step following ADEA methodology.

Usage

```

adea_hierarchical(
  input,
  output,
  orientation = c("input", "output"),
  load.orientation = c("inoutput", "input", "output"),
  name = "",
  direction = c("backward", "backward/input", "backward/output"),
  verbose = 0
)

```

Arguments

input	A matrix or a data frame with the inputs of units to be evaluated, one row for each DMU and one column for each input.
output	A matrix or a data frame with the outputs of units to be evaluated, one row for each DMU and one column for each output.
orientation	Use "input" for input orientation or use "output" for output orientation in DEA model.
load.orientation	It allows the selection of variables to be included in load analysis. Its default value is "inoutput" which means that all input and all output variables will be included. Use "input" or "output" to include only input or output variables in load analysis.
name	An optional descriptive name for the model. It will be shown in print and summary results.

direction	The direction in which the variables go in and out of the model. Until now, only backward option is implemented.
verbose	Use 0 for minimal output, only final model. 1 or more to get detailed information of each step. This option affects only to printed output but not the result.

Details

This procedure provides a list of all DEA models for all nested sets of variables.

In each model, the variable with lower value of load is dropped. In this case, the load of a new model can be lower than a previous one.

See examples for more details.

Value

A list with all computed models. So, you can retrieve each model individually.

See Also

[adea_parametric](#)

Examples

```
# Read data
data('cardealers4')
input <- cardealers4[, 1:2]
output <- cardealers4[, 3:4]

# Compute all dea models in hierarchical way
adea_hierarchical(input, output)
#      Load #Efficient Factors #Inputs #Outputs      Inputs      Outputs
# 4 0.6666667      2      4      2      2 Employees, Depreciation CarsSold, WorkOrders
# 3 0.9575672      2      3      1      2      Depreciation CarsSold, WorkOrders
# 2 1.0000000      1      2      1      1      Depreciation CarsSold

# Compute again and store result in sol.ah
sol.ah <- adea_hierarchical(input, output)

# Summary the model with 3 variables
summary(sol.ah$model[[3]])
# Model name:
# Orientation is input
# Inputs: Depreciation
# Outputs: CarsSold WorkOrders
# Load: 0.9575672
# Input loads: 1
# Output loads: 1.042433 0.9575672
# Summary of efficiencies:
# Mean      sd      Min.  1st Qu.  Median  3rd Qu.  Max.
# 0.9002232 0.1351949 0.6515044 0.8722527 0.9422250 0.9978982 1.0000000
# Efficiencies:
# Dealer A Dealer B Dealer C Dealer D Dealer E Dealer F
```

```
# 0.9915929 1.0000000 0.8928571 0.8653846 1.0000000 0.6515044

# Get efficiencies for the model with 3 variables
sol.ah$models[[3]]$eff
# Dealer A Dealer B Dealer C Dealer D Dealer E Dealer F
# 0.9915929 1.0000000 0.8928571 0.8653846 1.0000000 0.6515044
```

adea_loads

Compute the variables load ratios in DEA

Description

For the given input, output and two sets of weights, the function computes the loads of each variable for such values.

Usage

```
adea_loads(
  input,
  output,
  ux,
  vy,
  load.orientation = c("inoutput", "input", "output")
)
```

Arguments

input	A matrix or a data frame with the inputs of units to be evaluated, one row for each DMU and one column for each input.
output	A matrix or a data frame with the outputs of units to be evaluated, one row for each DMU and one column for each output.
ux	A matrix of weights for DMUs and input variables.
vy	A matrix of weights for DMUs and output variables.
load.orientation	It allows the selection of variables to be included in load analysis. Its default value is "inoutput" which means that all input and all output variables will be included. Use "input" or "output" to include only input or output variables in load analysis.

Details

In DEA analysis, even when the efficiency scores remain constants, there are a great level of freedom to select the sets of weights for input and output variables.

Not all those sets of weights attaches the same importance to the variables. This function allows to compute the load of each variable for the given weights in order to compare different sets of weights for the same efficiencies scores. Also compute load.levels which are the minimum value of such loads.

Take into account that different sets of weights means different ways to model the efficiency.

This function does not solve any model, only if u_x and v_y are the optimal values for the adea model, this function provides the load-levels as described in the theoretical adea model.

Value

Loads ratios and load for input and output variables

Examples

```
# Load data
data('cardealers4')
# Define input and output
input <- cardealers4[, 1:2]
output <- cardealers4[, 3:4]
# Make dea analysis
model <- dea(input, output, RTS = 'crs', DUAL = TRUE)
# Show results
model
# Compute loads for such weights
adea_loads(input, output, model$ux, model$vy)
```

adea_load_leverage	<i>Search for leverage units (DMU's) with higher impact on load levels in DEA analysis</i>
--------------------	--

Description

Search for leverage units (DMU's) with higher impact on load levels in DEA analysis.

Usage

```
adea_load_leverage(
  input,
  output,
  orientation = c("input", "output"),
  load.orientation = c("inoutput", "input", "output"),
  load.diff = 0.05,
  ndel = 1,
  nmax = 0
)
```

Arguments

input	A matrix or a data frame with the inputs of units to be evaluated, one row for each DMU and one column for each input.
-------	--

output	A matrix or a data frame with the outputs of units to be evaluated, one row for each DMU and one column for each output.
orientation	Use "input" for input orientation or use "output" for output orientation in DEA model.
load.orientation	It allows the selection of variables to be included in load analysis. Its default value is "inoutput" which means that all input and all output variables will be included. Use "input" or "output" to include only input or output variables in load analysis.
load.diff	Minimum difference in load to consider a subset of DMUs as a leverage one
ndel	Maximum number of units to drop out in each try.
nmax	Maximum number of DMU sets to include in results. 0 for no limit.

Value

The indexes of units with higher impact on load levels.

Note

This function has to solve a large number of large linear programs that grows with DMUs. So computation time required may be very large, be patient.

Examples

```
data('cardealers4')
input <- cardealers4[, 1:2]
output <- cardealers4[, 3:4]
adea_load_leverage(input, output, ndel = 2)
```

adea_parametric

Selection of an optimal subset of variables for DEA analysis

Description

The function returns a list of DEA models removing at least one variable in each step, to get a sequence of models with increasing values of adea loads.

Usage

```
adea_parametric(
  input,
  output,
  orientation = c("input", "output"),
  load.orientation = c("inoutput", "input", "output"),
  name = "",
  direction = c("backward", "backward/input", "backward/output"),
  verbose = 0
)
```

Arguments

input	A matrix or a data frame with the inputs of units to be evaluated, one row for each DMU and one column for each input.
output	A matrix or a data frame with the outputs of units to be evaluated, one row for each DMU and one column for each output.
orientation	Use "input" for input orientation or use "output" for output orientation in DEA model.
load.orientation	It allows the selection of variables to be included in load analysis. Its default value is "inoutput" which means that all input and all output variables will be included. Use "input" or "output" to include only input or output variables in load analysis.
name	An optional descriptive name for the model. It will be shown in print and summary results.
direction	The direction in which the variables go in and out of the model. Until now, only backward option is implemented.
verbose	Use 0 for minimal output, only final model. 1 or more to get detailed information of each step. This option affects only to printed output but not the result.

Details

This procedure provides a list of all DEA models for all different threshold for load values.

The models are sorted by increasing values of loads from initially given model to the one with one input and one output variable. Note that the load value for the model with one input and one output is 1. In each step at least one variable is dropped, but more than one can be dropped in each step.

See example for more details.

Value

A list with all computed models. So, you can retrieve each model individually.

See Also

[adea_hierarchical](#)

Examples

```
# Read data
data('cardealers4')
input <- cardealers4[, 1:2]
output <- cardealers4[, 3:4]

# Compute all dea models in parametric way
adea_parametric(input, output)
#      Load #Efficient Factors #Inputs #Outputs      Inputs      Outputs
# 4 0.6666667      2      4      2      2 Employees, Depreciation CarsSold, WorkOrders
# 3 0.9575672      2      3      1      2      Depreciation CarsSold, WorkOrders
```

```

# 2 1.0000000      1      2      1      1      Depreciation      CarsSold

# Compute again and store result in sol.ap
sol.ap <- adea_parametric(input, output)

# Summary the model with 3 variables
summary(sol.ap$models[[3]])
# Model name:
# Orientation is input
# Inputs: Depreciation
# Outputs: CarsSold WorkOrders
# Load: 0.9575672
# Input loads: 1
# Output loads: 1.042433 0.9575672
# Summary of efficiencies:
# Mean      sd      Min.  1st Qu.  Median  3rd Qu.  Max.
# 0.9002232 0.1351949 0.6515044 0.8722527 0.9422250 0.9978982 1.0000000
# Efficiencies:
# Dealer A Dealer B Dealer C Dealer D Dealer E Dealer F
# 0.9915929 1.0000000 0.8928571 0.8653846 1.0000000 0.6515044

# Get efficiencies for the model with 3 variables
sol.ap$models[[3]]$eff
# Dealer A Dealer B Dealer C Dealer D Dealer E Dealer F
# 0.9915929 1.0000000 0.8928571 0.8653846 1.0000000 0.6515044

```

adea_stepwise

Select an optimal subset of variables for DEA analysis

Description

Stepwise procedure for variable selection in DEA models. This is a back end function for `adea_hierarchical` and `adea_parametric` functions. So, it is not for end user use.

Usage

```

adea_stepwise(
  input,
  output,
  orientation = c("input", "output"),
  load.orientation = c("inoutput", "input", "output"),
  name = "",
  direction = c("backward", "backward/input", "backward/output"),
  load.critical = 0.5,
  max.steps = ncol(input) + ncol(output) - 2,
  verbose = 0
)

```

Arguments

input	A matrix or a data frame with the inputs of units to be evaluated, one row for each DMU and one column for each input.
output	A matrix or a data frame with the outputs of units to be evaluated, one row for each DMU and one column for each output.
orientation	Use "input" for input orientation or use "output" for output orientation in DEA model.
load.orientation	It allows the selection of variables to be included in load analysis. Its default value is "inoutput" which means that all input and all output variables will be included. Use "input" or "output" to include only input or output variables in load analysis.
name	An optional descriptive name for the model. It will be shown in print and summary results.
direction	The direction in which the variables go in and out of the model. Until now, only backward option is implemented.
load.critical	Minimum values for load.ratios to consider that a variable should be considered in the model. It can be also a vector with two values, the first value input loads and the second for output loads.
max.steps	The maximum number of steps allowed.
verbose	Use 0 for minimal output, only final model. 1 or more to get detailed information of each step. This option affects only to printed output but not the result.

Value

The function returns a DEA model with optimised set of variables.

cadea

Make a constrained ADEA analysis

Description

This function computes an efficiency score for each DMU and a load for each variable in the current model. But loads or contributions of input or output variables are constrained between the given values. So DMU's efficiencies could change from regular DEA or ADEA model.

Usage

```
cadea(
  input,
  output,
  orientation = c("input", "output"),
  load.orientation = c("inoutput", "input", "output"),
  name = "",
```

```

    load.min,
    load.max,
    eff.tolerance = 1e-04
)

```

Arguments

input	A matrix or a data frame with the inputs of units to be evaluated, one row for each DMU and one column for each input.
output	A matrix or a data frame with the outputs of units to be evaluated, one row for each DMU and one column for each output.
orientation	Use "input" for input orientation or use "output" for output orientation in DEA model.
load.orientation	It allows the selection of variables to be included in load analysis. Its default value is "inoutput" which means that all input and all output variables will be included. Use "input" or "output" to include only input or output variables in load analysis.
name	An optional descriptive name for the model. It will be shown in print and summary results.
load.min	A numeric value or vector giving minimum values for loads. Values for load.min must belongs to [0, 1).
load.max	A numeric value or vector giving maximum values for loads. Values for load.max must be greater than 1. If load.min or load.max are vectors then its length must be the same as the number of loads to compute. This means, number of inputs when load.orientation is input, number of outputs when load.orientation is output, and the sum of both when load.orientation is inoutput.
eff.tolerance	A value between 0 and 1 to tolerance when considering a DMU as efficient in reports.

Details

A variable load is a number between 0 and 1. Where 0 means that the contribution of that variable to the efficiency computations is negligible. In an ideal case, each input or output variable will have a load of 1 divide by the number of them. This model force input and output weights in such a way that final variable loads fall between the given values.

For more information about loads or ADEA model see [adea](#)

Value

The function returns an object with efficiency scores, one set of weights for inputs and other for outputs, number of efficient units, load ratios and load levels.

Note

If the given limits are too narrow, then the model is infeasible, which will result in an error.

See Also

[adea-package.](#)

Examples

```

data('cardealers4')
input <- cardealers4[, 1:2]
output <- cardealers4[, 3:4]

# Compute adea model
model <- adea(input, output)
model
# Dealer A Dealer B Dealer C Dealer D Dealer E Dealer F
# 0.9915929 1.0000000 0.8928571 0.8653846 1.0000000 0.6515044

# Get model load ratios
model$load$ratios
# $input
# Employees Depreciation
# 0.6666667 1.3333333
# $output
# CarsSold WorkOrders
# 1.2663476 0.7336524

# Compute a constrained adea model to force load between .8 and 1.5
cmodel <- cadea(input, output, load.min = .8, load.max = 1.5)
cmodel
# Dealer A Dealer B Dealer C Dealer D Dealer E Dealer F
# 0.9915929 1.0000000 0.8928571 0.8653846 1.0000000 0.6515044

# Get model load ratios
cmodel$load$ratios
# $input
# Employees Depreciation
# 0.8 1.2
# $output
# CarsSold WorkOrders
# 1.2 0.8

# See differences of efficiencies in both models
model$eff - cmodel$eff
# Dealer A Dealer B Dealer C Dealer D Dealer E Dealer F
# -2.220446e-16 0.000000e+00 0.000000e+00 0.000000e+00 0.000000e+00 5.942183e-02

```

cardealers1

A data set about car dealers, 1 of 4, to be used in DEA

Description

An example dataset with six car dealers data to be use in DEA (Data Envelopment Analysis).

Format

Employees: The number of employees in the car dealer to be considered as input variable in DEA.

Sold: The sold amount by the car dealer to be considered as output variable in DEA.

Details

The purpose of this dataframe is to be used in DEA (Data Envelopment Analysis). DEA rate each unit, in this case car dealers, in terms of efficiency. Less input and more output lead to higher efficiency scores.

Usage

```
data('cardealers1')
```

Source

Vicente Coll Serrano y Olga M. Blasco Blasco (2006) Evaluacion de la eficiencia mediante el analisis envolvente de datos. Electronic edition. <https://www.eumed.net/libros-gratis/2006c/197/>

See Also

See also [adea-package](#).

cardealers2

A data set about cardealers, 2 of 4, to be used in DEA

Description

An example dataset with six car dealers data to be use in DEA (Data Envelopment Analysis).

Format

Employess: The number of employees in the car dealer to be considered as input variable in DEA.

CarsSold: The number of car sold by the car dealer to be considered as output variable in DEA.

WorkOrders: The number of works orders for the mechanical garage to be considered as output variable in DEA.

Details

The purpose of this dataframe is to be used in DEA (Data Envelopment Analysis). DEA rate each unit, in this case car dealers, in terms of efficiency. Less input and more output lead to higher efficiency scores.

Usage

```
data('cardealers2')
```

Source

Vicente Coll Serrano y Olga M. Blasco Blasco (2006) Evaluacion de la eficiencia mediante el analisis envolvente de datos. Electronic edition. <https://www.eumed.net/libros-gratis/2006c/197/>

See Also

See also [adea-package](#).

cardealers3

A data set about car dealers, 3 of 4, to be used in DEA

Description

An example dataset with six car dealers data to be use in DEA (Data Envelopment Analysis).

Format

Employess: The number of employees in the car dealer to be considered as input variable in DEA.

Amortization: As an indirect measure of the capital invested to be considered as input variable in DEA.

NetSales: Net amount of sales to be considered as output variable in DEA.

Details

The purpose of this dataframe is to be used in DEA (Data Envelopment Analysis). DEA rate each unit, in this case car dealers, in terms of efficiency. Less input and more output lead to higher efficiency scores.

Usage

```
data('cardealers3')
```

Source

Vicente Coll Serrano y Olga M. Blasco Blasco (2006) Evaluacion de la eficiencia mediante el analisis envolvente de datos. Electronic edition. <https://www.eumed.net/libros-gratis/2006c/197/>

See Also

See also [adea-package](#).

`cardealers4`*A data set about car dealers, 4 of 4, to be used in DEA*

Description

An example dataset for six car dealers to be use in DEA (Data envelopment analysis).

Format

Employees: Number of employees to be considered as input variable in DEA.

Depreciation: Depreciation of stored to be considered as input variable in DEA.

Sold: Number of cars sold as output variable in DEA.

Orders: Number of work orders in garage as output variable in DEA.

Details

The purpose of this dataframe is to be used in DEA (Data Envelopment Analysis). DEA rate each unit, in this case car dealers, in terms of efficiency. Less input and more output lead to higher efficiency scores.

Usage

```
data('cardealers4')
```

Source

Vicente Coll Serrano y Olga M. Blasco Blasco (2006) Evaluacion de la eficiencia mediante el analisis envolvente de datos. Electronic edition. <https://www.eumed.net/libros-gratis/2006c/197/>

See Also

See also [adea-package](#).

`print.adea`*Print method for adea class*

Description

Print method for adea class

Usage

```
## S3 method for class 'adea'  
print(x, ...)
```

Arguments

x Object of class adea to print.
... Optional arguments to "print".

print.adeahierarchical
Print method for adeahierarchical class

Description

For the final model of adea_hierarchical function prints a summary, the input variables, and outputs variables.

Usage

```
## S3 method for class 'adeahierarchical'  
print(x, ...)
```

Arguments

x Object of class adeahierarchical to print.
... Optional arguments to "print".

print.adealoadleverage
Print method for adealoadleverage class

Description

Print adealoadleverage results in human readable way

Usage

```
## S3 method for class 'adealoadleverage'  
print(x, ...)
```

Arguments

x Object of class adealoadleverage to print.
... Optional arguments to "print".

print.adeaparametric *Print method for adeaparametric class*

Description

For the final model of adea_parametric function prints a summary, the input variables, and outputs variables.

Usage

```
## S3 method for class 'adeaparametric'  
print(x, ...)
```

Arguments

x Object of class adeaparametric to print.
... Optional arguments to "print".

print.adeastepwise *Print method for adeastepwise class*

Description

For the final model of adea_stepwise function prints a summary, the input variables, and outputs variables.

Usage

```
## S3 method for class 'adeastepwise'  
print(x, ...)
```

Arguments

x Object of class adeastepwise to print.
... Optional arguments to "print".

print.cadea	<i>Print method for cadea class</i>
-------------	-------------------------------------

Description

Print method for cadea class

Usage

```
## S3 method for class 'cadea'
print(x, ...)
```

Arguments

x	Object of class cadea to print.
...	Optional arguments to "print".

spanishuniversities2018	<i>A data set of Spanish public universities</i>
-------------------------	--

Description

Data set spanishuniversities2018 belongs to 47 public Spanish universities, all but Pais Vasco because its staff data is missing.

Format

TeachingStaff: number of people teaching and researching with a doctor degree.

FPU2018: number of predoctoral contracts with state funds done in 2018.

FPI2018: number of postdoctoral contracts with state funds done in 2018.

Patents: number of patents registered from 2013 and 2017.

PhDThesis: number of PhD Thesis in 2017/2018 academic year.

JCR: number of papers published in journals included in JCR index

Six: number of positive reports obtained in the state research evaluation program. All permanent teaching staff from Spanish universities can apply every six year for a program to get a positive evaluation of their research activities. Positive evaluations are considered merits for promotion and represent an increase in salary.

Projects: number of research projects financed with state funds obtained in competitive calls.

Details

The purpose of this dataframe is to be used in DEA (Data Envelopment Analysis).

The only one input variable is TeachingStaff.

The output variables are: TeachingStaff, FPU2018, FPI2018, Patens, PhDThesis, JCR, Six and Projects.

Usage

```
data('spanishuniversities2018')
```

Source

Data are taken from public available information systems.

See Also

See also [adea-package](#).

summary.adea

summary method for adea class

Description

summary method for adea class

Usage

```
## S3 method for class 'adea'  
summary(object, ...)
```

Arguments

object is the object of class adea to summarise
... optional arguments to 'print'

`summary.adeahierarchical`*Summary method for adeahierarchical class*

Description

For the final model of `adea_hierarchical` function print the model name, orientation, load orientation, a summary, the input variables, and outputs variables.

Usage

```
## S3 method for class 'adeahierarchical'  
summary(object, ...)
```

Arguments

<code>object</code>	Is the object of class <code>adeahierarchical</code> to summarise.
<code>...</code>	Optional arguments to "print".

`summary.adeaparametric`*summary method for adeaparametric class*

Description

For the final model of `adea_parametric` function print the model name, orientation, load orientation, a summary, the input variables, and outputs variables.

Usage

```
## S3 method for class 'adeaparametric'  
summary(object, ...)
```

Arguments

<code>object</code>	is the object of class <code>adeaparametric</code> to summarise
<code>...</code>	optional arguments to 'print'

summary.adeastepwise *Summary method for adeastepwise class*

Description

For the final model of adea_stepwise function print the model name, orientation, load orientation, a summary, the input variables, and outputs variables.

Usage

```
## S3 method for class 'adeastepwise'
summary(object, ...)
```

Arguments

object is the object of class adeastepwise to summarise.
 ... Optional arguments to "print".

summary.cadea *summary method for cadea class*

Description

summary method for cadea class

Usage

```
## S3 method for class 'cadea'
summary(object, ...)
```

Arguments

object is the object of class cadea to summarise
 ... optional arguments to 'print'

tokyo_libraries	<i>A data set of Tokyo libraries</i>
-----------------	--------------------------------------

Description

tokyo_libraries involves a set of 23 libraries in Tokyo and it has been used frequently in DEA literature.

Format

Area.I1: Area of library.

Books.I2: Number of books.

Staff.I3: Staff members.

Populations.I4: Population of influence area.

Regist.01: Registered people.

Borrow.02: Borrowed books.

Details

The purpose of this dataframe is to be used in DEA (Data Envelopment Analysis).

The input variables are Area.I1, Books.I2, Staff.I3 and Populations.I4.

The output variables are Regist.01 and Borrow.02.

Usage

```
data('tokyo_libraries')
```

See Also

See also [adea-package](#).

Index

* **DEA**

- adea-package, 2
- cardealers1, 15
- cardealers2, 16
- cardealers3, 17
- cardealers4, 18
- spanishuniversities2018, 21
- tokyo_libraries, 25

* **data**

- cardealers1, 15
- cardealers2, 16
- cardealers3, 17
- cardealers4, 18
- spanishuniversities2018, 21
- tokyo_libraries, 25

* **package**

- adea-package, 2

adea, 4, 14

adea-package, 2

adea_hierarchical, 6, 11

adea_load_leverage, 9

adea_loads, 8

adea_parametric, 7, 10

adea_stepwise, 12

cadea, 13

cardealers1, 15

cardealers2, 16

cardealers3, 17

cardealers4, 18

print.adea, 18

print.adeahierarchical, 19

print.adealoadleverage, 19

print.adeaparametric, 20

print.adeastepwise, 20

print.cadea, 21

spanishuniversities2018, 21

summary.adea, 22

summary.adeahierarchical, 23

summary.adeaparametric, 23

summary.adeastepwise, 24

summary.cadea, 24

tokyo_libraries, 25