

Package ‘Rmpi’

April 17, 2009

Version 0.5-7

Date 2009-2-20

Title Interface (Wrapper) to MPI (Message-Passing Interface)

Author Hao Yu

Maintainer Hao Yu <hyu@stats.uwo.ca>

Depends R (>= 2.2.0)

Suggests rsprng, rlecuyer

Description Rmpi provides an interface (wrapper) to MPI APIs. It also provides interactive R slave environment.

License GPL (>= 2)

URL <http://www.stats.uwo.ca/faculty/you/Rmpi>

Repository CRAN

Date/Publication 2009-02-20 19:27:02

R topics documented:

bin.nchar	2
lamhosts	3
mpi.abort	4
mpi.any.source	5
mpi.apply	6
mpi.applyLB	7
mpi.barrier	8
mpi.bcast	9
mpi.bcast.cmd	10
mpi.bcast.Robj	11
mpi.cart.coords	12
mpi.cart.create	13

mpi.cart.get	14
mpi.cart.rank	15
mpi.cart.shift	16
mpi.cartdim.get	17
mpi.comm.disconnect	18
mpi.comm.free	19
mpi.comm.get.parent	20
mpi.comm.set.errhandler	21
mpi.comm.size	21
mpi.comm.spawn	22
mpi.dims.create	23
mpi.exit	24
mpi.finalize	25
mpi.gather	26
mpi.gather.Robj	27
mpi.get.count	28
mpi.get.processor.name	29
mpi.get.sourcetag	30
mpi.iapplyLB	31
mpi.info.create	32
mpi.init.sprng	33
mpi.intercomm.merge	34
mpi.parSim	35
mpi.probe	37
mpi.realloc	38
mpi.reduce	39
mpi.remote.exec	40
mpi.scatter	41
mpi.scatter.Robj	42
mpi.send	43
mpi.send.Robj	45
mpi.sendrecv	46
mpi.setup.sprng	47
mpi.spawn.Rslaves	48
mpi.universe.size	50
mpi.wait	51

Index**53**

Description

Internal functions used by other MPI functions.

`bin.nchar` is used to find the number of char in a binary character vector (length 1) produced by `serialize`.

`mpi.comm.is.null` is used to test if a comm is `MPI_COMM_NULL` (empty members).

`string` create a string (empty space character) buffer.

Usage

```
bin.nchar(x)
mpi.comm.is.null(comm)
string(length)
```

Arguments

<code>comm</code>	a communicator number.
<code>x</code>	an R object.
<code>length</code>	length of a string.

Value

`bin.nchar` returns the length of a binary char vector.

`string` returns an empty character string.

Author(s)

Hao Yu

See Also

[mpi.spawn.Rslaves](#)

lamhosts

Hosts Information

Description

`lamhosts` finds the host name associated with its node number. Can be used by [mpi.spawn.Rslaves](#) to spawn R slaves on selected hosts. This is a LAM-MPI specific function.

`mpi.is.master` checks if it is running on master or slaves.

`mpi.hostinfo` finds an individual host information including rank and size in a comm.

`slave.hostinfo` is executed only by master and find all master and slaves host information in a comm.

`mpichhosts` finds host names from master Windows registry database.

Usage

```
lamhosts()  
mpi.is.master()  
mpi.hostinfo(comm = 1)  
slave.hostinfo(comm = 1)  
mpichhosts()
```

Arguments

comm a communicator number

Value

lamhosts returns CPUs nodes numbers with their host names.

mpi.is.master returns TRUE if it is on master and FALSE otherwise.

mpi.hostinfo sends to stdio a host name, rank, size and comm.

slave.hostname sends to stdio a list of host, rank, size, and comm information for all master and slaves.

mpichhosts returns hostnames including multiple same hostname if a host has multiple CPUs. The first host is labeled as "master", the rest is labeled as "slave1", "slave2", and so on. mpi.universe.size will return the length of mpichhosts-1 on Windows platform.

Author(s)

Hao Yu

See Also

[mpi.spawn.Rslaves](#)

mpi.abort

MPI_Abort API

Description

mpi.abort makes a "best attempt" to abort all tasks in a comm.

Usage

```
mpi.abort(comm = 1)
```

Arguments

comm a communicator number

Value

1 if success. Otherwise 0.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.finalize](#)

mpi.any.source *MPI Constants*

Description

Find MPI constants: MPI_ANY_SOURCE, MPI_ANY_TAG, or MPI_PROC_NULL

Usage

```
mpi.any.source()  
mpi.any.tag()  
mpi.proc.null()
```

Arguments

None

Details

These constants are mainly used by [mpi.send](#), [mpi.recv](#), and [mpi.probe](#). Different implementation of MPI may use different integers for MPI_ANY_SOURCE, MPI_ANY_TAG, and MPI_PROC_NULL. Hence one should use these functions instead real integers for MPI communications.

Value

Each function returns an integer value.

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.send](#), [mpi.recv](#).

mpi.apply

Scatter an array to slaves and then apply a fun

Description

An array (length \leq total number of slaves) is scattered to slaves so that the first slave calls `fun` with arguments `x[[1]]` and `...`, the second one calls with arguments `x[[2]]` and `...`, and so on. `mpi.iapply` is a nonblocking version of `mpi.apply` so that it will not consume CPU on master node.

Usage

```
mpi.apply(x, fun, ..., comm=1)
mpi.iapply(x, fun, ..., comm=1, sleep=0.001)
```

Arguments

<code>x</code>	an array
<code>fun</code>	a function
<code>...</code>	optional arguments to <code>fun</code>
<code>comm</code>	a communicator number
<code>sleep</code>	a sleep interval on master node (in sec)

Value

A list of the results is returned. Its length is the same as that of `x`. In case the call `fun` with arguments `x[[i]]` and `...` fails on `i`th slave, corresponding error message will be returned in the returning list.

Author(s)

Hao Yu

Examples

```
## Not run:
#Assume that there are at least 5 slaves running
#Otherwise run mpi.spawn.Rslaves(nslaves=5)
x=c(10,20)
mpi.apply(x,runif)
meanx=1:5
mpi.apply(meanx,rnorm,n=2,sd=4)
## End(Not run)
```

mpi.applyLB *(Load balancing) parallel apply*

Description

(Load balancing) parallel apply and related functions.

Usage

```
mpi.applyLB(x, fun, ..., apply.seq=NULL, comm=1)
mpi.parApply(x, MARGIN, fun, ..., job.num = mpi.comm.size(comm)-1,
             apply.seq=NULL, comm=1)
mpi.parLapply(x, fun, ..., job.num=mpi.comm.size(comm)-1, apply.seq=NULL, comm=1)
mpi.parSapply(x, fun, ..., job.num=mpi.comm.size(comm)-1, apply.seq=NULL, simplify=
             USE.NAMES = TRUE, comm=1)
mpi.parRapply(x, fun, ..., job.num=mpi.comm.size(comm)-1, apply.seq=NULL, comm=1)
mpi.parCapply(x, fun, ..., job.num=mpi.comm.size(comm)-1, apply.seq=NULL, comm=1)
mpi.parReplicate(n, expr, job.num=mpi.comm.size(comm)-1, apply.seq=NULL, simplify =
```

Arguments

x	an array or matrix.
MARGIN	vector specifying the dimensions to use.
fun	a function.
simplify	logical; should the result be simplified to a vector or matrix if possible?
USE.NAMES	logical; if TRUE and if x is character, use x as names for the result unless it had names already.
n	number of replications.
expr	expression to evaluate repeatedly.
job.num	Total job numbers. If job numbers is bigger than total slave numbers (default value), a load balancing approach is used.
apply.seq	if reproducing the same computation (simulation) is desirable, set it to the integer vector .mpi.applyLB generated in previous computation (simulation).
...	optional arguments to fun
comm	a communicator number

Details

Unless length of x is no more than total slave numbers (slave.num) and in this case mpi.applyLB is the same as mpi.apply, mpi.applyLB sends a next job to a slave who just delivered a finished job. The sequence of slaves who deliver results to master are saved into .mpi.applyLB. It keeps track which part of results done by which slaves. .mpi.applyLB can be used to reproduce the same simulation result if the same seed is used and the argument apply.seq is equal to .mpi.applyLB.

With the default value of argument `job.num` which is `slave.num`, `mpi.parApply`, `mpi.parLapply`, `mpi.parSapply`, `mpi.parRapply`, `mpi.parCapply`, and `mpi.parSapply` are clones of `snow`'s `parApply`, `parLapply`, `parSapply`, `parRapply`, `parCapply`, and `parSapply`, respectively. When `job.num` is bigger than `slave.num`, a load balancing approach is used.

Warning

When using the argument `apply.seq` with `.mpi.applyLB`, be sure all settings are the same as before, i.e., the same data, `job.num`, `slave.num`, and `seed`. Otherwise a deadlock could occur. Notice that `apply.seq` is useful only if `job.num` is bigger than `slave.num`.

See Also

[mpi.apply](#)

Examples

```
## Not run:
#Assume that there are some slaves running

#mpi.applyLB
x=1:7
mpi.applyLB(x, rnorm, mean=2, sd=4)

#get the same simulation
mpi.remote.exec(set.seed(111))
mpi.applyLB(x, rnorm, mean=2, sd=4)
mpi.remote.exec(set.seed(111))
mpi.applyLB(x, rnorm, mean=2, sd=4, apply.seq=.mpi.applyLB)

#mpi.parApply
x=1:24
dim(x)=c(2, 3, 4)
mpi.parApply(x, MARGIN=c(1,2), fun=mean, job.num = 5)

#mpi.parLapply
mdat <- matrix(c(1,2,3, 7,8,9), nrow = 2, ncol=3, byrow=TRUE,
                dimnames = list(c("R.1", "R.2"), c("C.1", "C.2", "C.3")))
mpi.parLapply(mdat, rnorm)

#mpi.parSapply
mpi.parSapply(mdat, rnorm)
## End(Not run)
```

mpi.barrier

MPI_Barrier API

Description

`mpi.barrier` blocks the caller until all members have called it.

Usage

```
mpi.barrier(comm = 1)
```

Arguments

comm a communicator number

Value

1 if success. Otherwise 0.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

mpi.bcast

MPI_Bcast API

Description

mpi.bcast is a collective call among all members in a comm. It broadcasts a message from the specified rank to all members.

Usage

```
mpi.bcast(x, type, rank = 0, comm = 1)
```

Arguments

x data to be sent or received. Must be the same type among all members.
 type 1 for integer, 2 for double, and 3 for character. Others are not supported.
 rank the sender.
 comm a communicator number.

Details

mpi.bcast is a blocking call among all members in a comm, i.e, all members have to wait until everyone calls it. All members have to prepare the same type of messages (buffers). Hence it is relatively difficult to use in R environment since the receivers may not know what types of data to receive, not mention the length of data. Users should use various extensions of mpi.bcast in R. They are [mpi.bcast.Robj](#), [mpi.bcast.cmd](#), and [mpi.bcast.Robj2slave](#).

Value

mpi.bcast returns the message broadcasted by the sender (specified by the rank).

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

mpi.bcast.Robj, mpi.bcast.cmd, mpi.bcast.Robj2slave.

mpi.bcast.cmd *Extension of MPI_Bcast API*

Description

mpi.bcast.cmd is an extension of [mpi.bcast](#). It is mainly used to transmit a command from master to all R slaves spawned by using `slavedaemon.R` script.

Usage

```
mpi.bcast.cmd(cmd=NULL, rank = 0, comm = 1)
```

Arguments

cmd	a command to be sent for master.
rank	the sender
comm	a communicator number

Details

[deparse](#) is used to convert a command into a char vector. Some syntax errors of the command will be automatically detected by `deparse`. Then the char vector is broadcasted to all members. After receiving the char vector, the receivers use [parse](#) to convert the char vector into an expression. Finally `slavedaemon.R` script will evaluate this expression. Hence `mpi.bcast.cmd` is only used by `slavedaemon.R`, or by whatever a R script based on `slavedaemon.R`. Please use [mpi.remote.exec](#) if you want the executed results returned from R slaves.

Value

mpi.bcast.cmd returns no value for the sender and an expression of the transmitted command for others.

Author(s)

Hao Yu

See Also

[mpi.remote.exec](#)

mpi.bcast.Robj *Extensions of MPI_Bcast API*

Description

mpi.bcast.Robj and mpi.bcast.Robj2slave are used to move a general R object around among master and all slaves.

Usage

```
mpi.bcast.Robj(obj = NULL, rank = 0, comm = 1)
mpi.bcast.Robj2slave(obj, comm = 1)
```

Arguments

obj	an R object to be transmitted from the sender
rank	the sender.
comm	a communicator number.

Details

mpi.bcast.Robj is an extension of [mpi.bcast](#) for moving a general R object around from a sender to everyone. mpi.bcast.Robj2slave does an R object transmission from master to all slaves only. serialize package is used to serialize/unserialize an R object.

Value

mpi.bcast.Robj returns no value for the sender and the transmitted one for others. mpi.bcast.Robj2slave returns no value for the master and the transmitted R object along its name on slaves.

Author(s)

Hao Yu

See Also

[mpi.send.Robj](#), [mpi.recv.Robj](#),

mpi.cart.coords *MPI_Cart_coords*

Description

mpi.cart.coords translates a rank to its Cartesian topology coordinate.

Usage

```
mpi.cart.coords(comm=3, rank, maxdims)
```

Arguments

comm	Communicator with Cartesian structure
rank	rank of a process within group
maxdims	length of vector coord in the calling program

Details

This function is the rank-to-coordinates translator. It is the inverse map of mpi.cart.rank. maxdims is at least as big as ndims as returned by mpi.cartdim.get.

Value

mpi.cart.coords returns an integer array containing the Cartesian coordinates of specified process.

Author(s)

Alek Hunchak and Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.cart.rank](#)

Examples

```
## Not run:
#Need at least 9 slaves
mpi.bcast.cmd(mpi.cart.create(1,c(3,3),c(F,T)))
mpi.cart.create(1,c(3,3),c(F,T))
mpi.cart.coords(3,4,2)
## End(Not run)
```

mpi.cart.create *MPI_Cart_create*

Description

mpi.cart.create creates a Cartesian structure of arbitrary dimension.

Usage

```
mpi.cart.create(commold=1, dims, periods, reorder=FALSE, commcart=3)
```

Arguments

commold	Input communicator
dims	Integery array of size ndims specifying the number of processes in each dimension
periods	Logical array of size ndims specifying whether the grid is periodic or not in each dimension
reorder	ranks may be reordered or not
commcart	The new communicator to which the Cartesian topology information is attached

Details

If reorder = false, then the rank of each process in the new group is the same as its rank in the old group. If the total size of the Cartesian grid is smaller than the size of the group of commold, then some processes are returned mpi.comm.null. The call is erroneous if it specifies a grid that is larger than the group size.

Value

mpi.cart.create returns 1 if success and 0 otherwise.

Author(s)

Alek Hunchak and Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

Examples

```
## Not run:  
#Need at least 9 slaves  
mpi.bcast.cmd(mpi.cart.create(1, c(3,3), c(F,T)))  
mpi.cart.create(1, c(3,3), c(F,T))  
## End(Not run)
```

mpi.cart.get	<i>MPI_Cart_get</i>
--------------	---------------------

Description

mpi.cart.get provides the user with information on the Cartesian topology associated with a comm.

Usage

```
mpi.cart.get(comm=3, maxdims)
```

Arguments

comm	Communicator with Cartesian structure
maxdims	length of vectors dims, periods, and coords in the calling program

Details

The coords are as given for the rank of the calling process as shown.

Value

mpi.cart.get returns a vector containing information on the Cartesian topology associated with comm. maxdims must be at least ndims as returned by mpi.cartdim.get.

Author(s)

Alek Hunchak and Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.cart.create](#), [mpi.cart.create](#)

Examples

```
## Not run:  
#Need at least 9 slaves  
mpi.bcast.cmd(mpi.cart.create(1,c(3,3),c(F,T)))  
mpi.cart.create(1,c(3,3),c(F,T))  
mpi.remote.exec(mpi.cart.get(3,2))  
## End(Not run)
```

mpi.cart.rank	<i>MPI_Cart_rank</i>
---------------	----------------------

Description

mpi.cart.rank translates a Cartesian topology coordinate to its rank.

Usage

```
mpi.cart.rank(comm=3, coords)
```

Arguments

comm	Communicator with Cartesian structure
coords	Specifies the Cartesian coordinates of a process

Details

For a process group with a Cartesian topology, this function translates the logical process coordinates to process ranks as they are used by the point-to-point routines. It is the inverse map of mpi.cart.coords.

Value

mpi.cart.rank returns the rank of the specified process.

Author(s)

Alek Hunchak and Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.cart.coords](#)

Examples

```
## Not run:  
#Need at least 9 slaves  
mpi.bcast.cmd(mpi.cart.create(1,c(3,3),c(F,T)))  
mpi.cart.create(1,c(3,3),c(F,T))  
mpi.cart.rank(3,c(1,0))  
## End(Not run)
```

mpi.cart.shift *MPI_Cart_shift*

Description

mpi.cart.shift shifts the Cartesian topology in both manners, displacement and direction.

Usage

```
mpi.cart.shift(comm=3, direction, disp)
```

Arguments

comm	Communicator with Cartesian structure
direction	Coordinate dimension of the shift
disp	displacement (>0 for upwards or left shift, <0 for downwards or right shift)

Details

mpi.cart.shift provides neighbor ranks from given direction and displacement. The direction argument indicates the dimension of the shift. direction=1 means the first dim, direction=2 means the second dim, etc. disp=1 or -1 provides immediate neighbor ranks and disp=2 or -2 provides neighbor's neighbor ranks. Negative ranks mean out of boundary. They correspond to mpi.proc.null.

Value

mpi.cart.shift returns a vector containing information regarding the rank of the source process and rank of the destination process.

Author(s)

Alek Hunchak and Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.cart.create](#), [mpi.proc.null](#)

Examples

```
## Not run:
#Need at least 9 slaves
mpi.bcast.cmd(mpi.cart.create(1,c(3,3),c(F,T)))
mpi.cart.create(1,c(3,3),c(F,T))
mpi.remote.exec(mpi.cart.shift(3,2,1))#get neighbor ranks
mpi.remote.exec(mpi.cart.shift(3,1,1))
## End(Not run)
```

mpi.cartdim.get *MPI_Cartdim_get*

Description

mpi.cartdim.get gets dim information about a Cartesian topology.

Usage

```
mpi.cartdim.get(comm=3)
```

Arguments

comm Communicator with Cartesian structure

Details

Can be used to provide other functions with the correct size of arrays.

Value

mpi.cartdim.get returns the number of dimensions of the Cartesian structure

Author(s)

Alek Hunchak and Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.cart.get](#)

Examples

```
## Not run:
#Need at least 9 slaves
mpi.bcast.cmd(mpi.cart.create(1,c(3,3),c(F,T)))
mpi.cart.create(1,c(3,3),c(F,T))
mpi.cartdim.get(comm=3)
## End(Not run)
```

```
mpi.comm.disconnect
```

MPI_Comm_disconnect API

Description

`mpi.comm.disconnect` disconnects itself from a communicator and then deallocates the communicator so it points to `MPI_COMM_NULL`.

Usage

```
mpi.comm.disconnect(comm=1)
```

Arguments

`comm` a communicator number

Details

When members associated with a communicator finish jobs or exit, they have to call `mpi.comm.disconnect` to release resource if the communicator was created from an intercommunicator by `mpi.intercomm.merge`. If `mpi.comm.free` is used instead, `mpi.finalize` called by slaves may cause undefined impacts on master who wishes to stay.

Value

1 if success. Otherwise 0.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.comm.free](#)

mpi.comm.free	<i>MPI_Comm_free</i> API
---------------	--------------------------

Description

mpi.comm.free deallocates a communicator so it points to MPI_COMM_NULL.

Usage

```
mpi.comm.free(comm=1)
```

Arguments

comm a communicator number

Details

When members associated with a communicator finish jobs or exit, they have to call `mpi.comm.free` to release resource so `mpi.comm.size` will return 0. If the comm was created from an intercommunicator by `mpi.intercomm.merge`, use `mpi.comm.disconnect` instead.

Value

1 if success. Otherwise 0.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.comm.disconnect](#)

```
mpi.comm.get.parent
```

```
    MPI_Comm_get_parent,  
    MPI_Comm_test_inter APIs
```

```
    MPI_Comm_remote_size,
```

Description

`mpi.comm.get.parent` is mainly used by slaves to find the intercommunicator or the parent who spawns them. The intercommunicator is saved in the specified comm number.

`mpi.comm.remote.size` is mainly used by master to find the total number of slaves spawned.

`mpi.comm.test.inter` tests if a comm is an intercomm or not.

Usage

```
mpi.comm.get.parent(comm = 2)  
mpi.comm.remote.size(comm = 2)  
mpi.comm.test.inter(comm = 2)
```

Arguments

`comm` an intercommunicator number.

Value

`mpi.comm.get.parent` and `mpi.comm.test.inter` return 1 if success and 0 otherwise.

`mpi.comm.remote.size` returns the total number of members in the remote group in an intercomm.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.intercomm.merge](#)

```
mpi.comm.set.errhandler
```

MPI_Comm_set_errhandler API

Description

`mpi.comm.set.errhandler` sets a communicator to `MPI_ERRORS_RETURN` instead of `MPI_ERRORS_ARE_FATAL` (default) which crashes R on any type of MPI errors. Almost all MPI API calls return errcodes which can map to specific MPI error messages. All MPI related error messages come from predefined `MPI_Error_string`.

Usage

```
mpi.comm.set.errhandler(comm = 1)
```

Arguments

`comm` a communicator number

Value

1 if success. Otherwise 0.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

```
mpi.comm.size
```

MPI_Comm_dup, MPI_Comm_rank. and MPI_Comm_size APIs

Description

`mpi.comm.dup` duplicates (copies) a comm to a new comm. `mpi.comm.rank` returns its rank in a comm. `mpi.comm.size` returns the total number of members in a comm.

Usage

```
mpi.comm.dup(comm, newcomm)
mpi.comm.rank(comm = 1)
mpi.comm.size(comm = 1)
```

Arguments

comm	a communicator number
newcomm	a new communicator number

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

Examples

```
## Not run:
#Assume that there are some slaves running
mpi.comm.size(comm=1)
mpi.comm.size(comm=0)

mpi.remote.exec(mpi.comm.rank(comm=1))
mpi.remote.exec(mpi.comm.rank(comm=0))

mpi.remote.exec(mpi.comm.size(comm=1))
mpi.remote.exec(mpi.comm.size(comm=0))

mpi.bcast.cmd(mpi.comm.dup(comm=1,newcomm=5))
mpi.comm.dup(comm=1,newcomm=5)
## End(Not run)
```

mpi.comm.spawn	<i>MPI_Comm_spawn API</i>
----------------	---------------------------

Description

mpi.comm.spawn tries to start nslaves identical copies of slaves, establishing communication with them and returning an intercommunicator. The spawned slaves are referred to as children, and the process that spawned them is called the parent (master). The children have their own MPI_COMM_WORLD represented by comm 0. To make communication possible among master and slaves, all slaves should use `mpi.comm.get.parent` to find their parent and use `mpi.intercomm.merge` to merger an intercomm to a comm.

Usage

```
mpi.comm.spawn(slave, slavearg = character(0),
              nslaves = mpi.universe.size(), info = 0,
              root = 0, intercomm = 2)
```

Arguments

slave	a file name to an executable program.
slavearg	an argument list (a char vector) to slave.
nslaves	number of slaves to be spawned.
info	an info number.
root	the root member who spawns slaves.
intercomm	an intercomm number.

Value

A message is printed to indicate how many slaves are successfully spawned and how many failed.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.comm.get.parent](#), [mpi.intercomm.merge](#).

mpi.dims.create *MPI_Dims_create*

Description

mpi.dims.create Create a Cartesian dimension used by mpi.cart.create.

Usage

```
mpi.dims.create(nnodes, ndims, dims=integer(ndims))
```

Arguments

nnodes	Number of nodes in a cluster
ndims	Number of dimension in a Cartesian topology
dims	Initial dimension numbers

Details

The entries in the return value are set to describe a Cartesian grid with ndims dimensions and a total of nnodes nodes. The dimensions are set to be as close to each other as possible, using an appropriate divisibility algorithm. The return value can be constrained by specifying positive number(s) in dims. Only those 0 values in dims are modified by mpi.dims.create.

Value

`mpi.dims.create` returns the dimension vector used by that in `mpi.cart.create`.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.cart.create](#)

Examples

```
#What is the dim numbers of 2 dim Cartersian topology under a grid of 36 nodes
mpi.dims.create(36,2) #return c(6,6)
#Constrained dim numbers
mpi.dims.create(12,2,c(0,4)) #return c(9,4)
```

`mpi.exit`

Exit MPI Environment

Description

`mpi.exit` terminates MPI execution environment and detaches the library Rmpi. After that, you can still work on R.

`mpi.quit` terminates MPI execution environment and quits R.

Usage

```
mpi.exit()
mpi.quit(save = "no")
```

Arguments

`save` the same argument as `quit` but default to "no".

Details

Normally, `mpi.finalize` is used to clean all MPI states. However, it will not detach the library Rmpi. To be more safe leaving MPI, `mpi.exit` not only calls `mpi.finalize` but also detaches the library Rmpi. This will make reload the library Rmpi impossible.

If leaving MPI and R altogether, one simply uses `mpi.quit`.

Value

`mpi.exit` always returns 1

Author(s)

Hao Yu

See Also

[mpi.finalize](#)

<code>mpi.finalize</code>	<i>MPI_Finalize API</i>
---------------------------	-------------------------

Description

Terminates MPI execution environment.

Usage

```
mpi.finalize()
```

Arguments

None

Details

This routines must be called by each slave (master) before it exists. This call cleans all MPI state. Once `mpi.finalize` has been called, no MPI routine may be called. To be more safe leaving MPI, please use [mpi.exit](#) which not only calls `mpi.finalize` but also detaches the library Rmpi. This will make reload the library Rmpi impossible.

Value

Always return 1

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.exit](#)

mpi.gather	<i>MPI_Gather, MPI_Gatherv, MPI_Allgather, and MPI_Allgatherv APIs</i>
------------	--

Description

mpi.gather and mpi.gatherv (vector variant) gather each member's message to the member specified by the argument *root*. The root member receives the messages and stores them in rank order. mpi.allgather and mpi.allgatherv are the same as mpi.gather and mpi.gatherv except that all members receive the result instead of just the root.

Usage

```
mpi.gather(x, type, rdata, root = 0, comm = 1)
mpi.gatherv(x, type, rdata, rcounts, root = 0, comm = 1)

mpi.allgather(x, type, rdata, comm = 1)
mpi.allgatherv(x, type, rdata, rcounts, comm = 1)
```

Arguments

<i>x</i>	data to be gathered. Must be the same type.
<i>type</i>	1 for integer, 2 for double, and 3 for character. Others are not supported.
<i>rdata</i>	the receive buffer. Must be the same type as the sender and big enough to include all message gathered.
<i>rcounts</i>	int vector specifying the length of each message.
<i>root</i>	rank of the receiver
<i>comm</i>	a communicator number

Details

For mpi.gather and mpi.allgather, the message to be gathered must be the same dim and the same type. The receive buffer can be prepared as either integer(size * dim) or double(size * dim), where size is the total number of members in a comm. For mpi.gatherv and mpi.allgatherv, the message to be gathered can have different dims but must be the same type. The argument *rcounts* records these different dims into an integer vector in rank order. Then the receive buffer can be prepared as either integer(sum(rcounts)) or double(sum(rcounts)).

Value

For mpi.gather or mpi.gatherv, it returns the gathered message for the root member. For other members, it returns what is in rdata, i.e., rdata (or rcounts) is ignored. For mpi.allgather or mpi.allgatherv, it returns the gathered message for all members.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

`mpi.scatter`, `mpi.scatterv`.

Examples

```
## Not run:
#Need 3 slaves to run properly
#Or use mpi.spawn.Rslaves(nslaves=3)
  mpi.bcast.cmd(id <-mpi.comm.rank(.comm), comm=1)
mpi.bcast.cmd(mpi.gather(letters[id],type=3,rdata=string(1)))
mpi.gather(letters[10],type=3,rdata=string(4))

  mpi.bcast.cmd(x<-rnorm(id))
  mpi.bcast.cmd(mpi.gatherv(x,type=2,rdata=double(1),rcounts=1))
  mpi.gatherv(double(1),type=2,rdata=double(sum(1:3)+1),rcounts=c(1,1:3))

mpi.bcast.cmd(out1<-mpi.allgatherv(x,type=2,rdata=double(sum(1:3)+1),rcounts=c(1,1:3)))
mpi.allgatherv(double(1),type=2,rdata=double(sum(1:3)+1),rcounts=c(1,1:3))
## End(Not run)
```

mpi.gather.Robj *Extentions of MPI_Gather and MPI_Allgather APIs*

Description

`mpi.gather.Robj` gathers each member's object to the member specified by the argument `root`. The root member receives the objects as a list. `mpi.allgather.Robj` is the same as `mpi.gather.Robj` except that all members receive the result instead of just the root.

Usage

```
mpi.gather.Robj(obj=NULL, root = 0, comm = 1)
```

```
mpi.allgather.Robj(obj=NULL, comm = 1)
```

Arguments

<code>obj</code>	data to be gathered. Could be different type.
<code>root</code>	rank of the gather
<code>comm</code>	a communicator number

Value

For `mpi.gather.Robj`, it returns a list, the gathered message for the root member. For `mpi.allgather.Robj`, it returns a list, the gathered message for all members.

Author(s)

Hao Yu and Wei Xia

References<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>**See Also**[mpi.gather](#), [mpi.allgatherv](#).**Examples**

```
## Not run:
#Assume that there are some slaves running
mpi.bcast.cmd(id<-mpi.comm.rank())
mpi.bcast.cmd(x<-rnorm(id))
mpi.bcast.cmd(mpi.gather.Robj(x))
x<-"test mpi.gather.Robj"
mpi.gather.Robj(x)

mpi.bcast.cmd(obj<-rnorm(id+10))
mpi.bcast.cmd(nn<-mpi.allgather.Robj(obj))
obj<-rnorm(5)
mpi.allgather.Robj(obj)
mpi.remote.exec(nn)
## End(Not run)
```

`mpi.get.count`*MPI_Get_count API*

Description`mpi.get.count` finds the length of a received message.**Usage**`mpi.get.count(type, status = 0)`**Arguments**

<code>type</code>	1 for integer, 2 for double, 3 for char.
<code>status</code>	a status number

Details

When `mpi.recv` is used to receive a message, the receiver buffer can be set to be bigger than the incoming message. To find the exact length of the received message, `mpi.get.count` is used to find its exact length. `mpi.get.count` must be called immediately after calling `mpi.recv` otherwise the status may be changed.

Value

the length of a received message.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

`mpi.send`, `mpi.recv`, `mpi.get.sourcetag`, `mpi.probe`.

`mpi.get.processor.name`

MPI_Get_processor_name API

Description

`mpi.get.processor.name` returns the host name (a string) where it is executed.

Usage

```
mpi.get.processor.name(short = TRUE)
```

Arguments

`short` a logical.

Value

a base host name if `short = TRUE` and a full host name otherwise.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

mpi.get.sourcetag *Utility for finding the source and tag of a received message*

Description

mpi.get.sourcetag finds the source and tag of a received message.

Usage

```
mpi.get.sourcetag(status = 0)
```

Arguments

status a status number

Details

When `mpi.any.source` and/or `mpi.any.tag` are used by `mpi.recv` or `mpi.probe`, one can use `mpi.get.sourcetag` to find who sends the message or with what a tag number. `mpi.get.sourcetag` must be called immediately after calling `mpi.recv` or `mpi.probe` otherwise the obtained information may not be right.

Value

2 dim int vector. The first integer is the source and the second is the tag.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

`mpi.send`, `mpi.recv`, `mpi.probe`, `mpi.get.count`

mpi.iapplyLB *(Load balancing) parallel apply with nonblocking features*

Description

(Load balancing) parallel apply and related functions.

Usage

```

mpi.iapplyLB(x, fun, ..., apply.seq=NULL, comm=1, sleep=0.001)
mpi.iparApply(x, MARGIN, fun, ..., job.num = mpi.comm.size(comm)-1,
              apply.seq=NULL, comm=1, sleep=0.001)
mpi.iparLapply(x, fun, ..., job.num=mpi.comm.size(comm)-1, apply.seq=NULL,
              comm=1, sleep=0.001)
mpi.iparSapply(x, fun, ..., job.num=mpi.comm.size(comm)-1, apply.seq=NULL,
              simplify=TRUE, USE.NAMES = TRUE, comm=1, sleep=0.001)
mpi.iparRapply(x, fun, ..., job.num=mpi.comm.size(comm)-1, apply.seq=NULL,
              comm=1, sleep=0.001)
mpi.iparCapply(x, fun, ..., job.num=mpi.comm.size(comm)-1, apply.seq=NULL,
              comm=1, sleep=0.001)
mpi.iparReplicate(n, expr, job.num=mpi.comm.size(comm)-1, apply.seq=NULL,
                 simplify = TRUE, comm=1, sleep=0.001)

```

Arguments

x	an array or matrix.
MARGIN	vector specifying the dimensions to use.
fun	a function.
simplify	logical; should the result be simplified to a vector or matrix if possible?
USE.NAMES	logical; if TRUE and if x is character, use x as names for the result unless it had names already.
n	number of replications.
expr	expression to evaluate repeatedly.
job.num	Total job numbers. If job numbers is bigger than total slave numbers (default value), a load balancing approach is used.
apply.seq	if reproducing the same computation (simulation) is desirable, set it to the integer vector .mpi.applyLB generated in previous computation (simulation).
...	optional arguments to fun
comm	a communicator number
sleep	a sleep interval on master node (in sec)

Details

mpi.iparApply, mpi.iparLapply, mpi.iparSapply, mpi.iparRapply, mpi.iparCapply, mpi.iparSapply, and mi.iparReplicate are nonblocking versions of mpi.parApply, mpi.parLapply, mpi.parSapply, mpi.parRapply, mpi.parCapply, mpi.parSapply, and mpi.parReplicate, respectively. The main difference is that mpi.iprobe and Sys.sleep are used so that master node consumes almost no CPU cycles while waiting for slaves results. However, due to frequent wake/sleep cycles on master, those functions are not suitable for running small jobs on slave nodes. If anticipated computing time for each job is relatively long, e.g., minutes or hours, setting sleep to be 1 second or longer will further reduce load on master (only slightly).

See Also

[mpi.iapply](#)

mpi.info.create *MPI_Info_create, MPI_Info_free, MPI_Info_get, MPI_Info_set APIs*

Description

Many MPI APIs take an info argument for additional information passing. An info is an object which consists of many (key,value) pairs. Rmpi uses an internal memory to store an info object.

mpi.info.create creates a new info object.

mpi.info.free frees an info object and sets it to MPI_INFO_NULL.

mpi.info.get retrieves the value associated with key in an info.

mpi.info.set adds the key and value pair to info.

Usage

```
mpi.info.create(info = 0)
mpi.info.free(info = 0)
mpi.info.get(info = 0, key, valuelen)
mpi.info.set(info = 0, key, value)
```

Arguments

info	an info number.
key	a char (length 1).
valuelen	the length (nchar) of a key
value	a char (length 1).

Value

mpi.info.create, mpi.info.free, and mpi.info.set return 1 if success and 0 otherwise.

mpi.info.get returns the value (a char) for a given info and valuelen.

Author(s)

Hao Yu

See Also[mpi.spawn.Rslaves](#)

mpi.init.sprng *Interface to rsprng for initializing SPRNG*

Description

mpi.init.sprng is used to initialize the parallel random number generator (PRNG) states in MPI environment. It is a collective call so all members in a comm must call it together.

Usage

```
mpi.init.sprng(seed = runif(1, 1, 2^31-1),
               kindprng = "default",
               para = 0,
               rank = 0,
               comm = 1)
```

Arguments

seed	an integer of random number seed.
kindprng	a character string of the desired kind of parallel random number generator.
para	additional parameters for the parallel random number generators. If para is 0, default parameters for each PRNG are used. When invalid parameter is given, a warning is issued and the default parameter is used.
rank	the sender who distributes seed, kindprng, para to other members in a comm, i.e., other members' seed, kindprng, and para are ignored.
comm	a comm number.

Value

Return the a two-element character vector of the RNG and normal kinds in use before the call.

Warning

When sprng is not used any more, please run [free.sprng](#) on all slaves and master to set back to R default RNG. If not doing so, an error message will come out like ".Random.seed[1] = 5 but no user-supplied generator" in the next session. One quick remedy is `rm(.Random.seed)`.

Author(s)

Hao Yu

References

SPRNG: Scalable Parallel Random Number Generator Library Web Page. <http://sprng.cs.fsu.edu/>

See Also

[init.sprng](#)

`mpi.intercomm.merge`

MPI_Intercomm_merge API

Description

Creates an intracommunicator from an intercommunicator

Usage

```
mpi.intercomm.merge(intercomm=2, high=0, comm=1)
```

Arguments

<code>intercomm</code>	an intercommunicator number
<code>high</code>	Used to order the groups of the two intracommunicators within <code>comm</code> when creating the new communicator
<code>comm</code>	a (intra)communicator number

Details

When master spawns slaves, an intercommunicator is created. To make communications (point-to-point or groupwise) among master and slaves, an intracommunicator must be created. `mpi.intercomm.merge` is used for that purpose. This is a collective call so all master and slaves call together. R slaves spawned by `mpi.spawn.Rslaves` should use `mpi.comm.get.parent` to get (set) an intercomm to a number followed by merging `intercomm` to an `intracomm`. One can use `mpi.comm.test.inter` to test if a communicator is an intercommunicator or not.

Value

1 if success. Otherwise 0.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.comm.test.inter](#)

 mpi.parSim

Parallel Monte Carlo Simulation

Description

Carry out parallel Monte Carlo simulation on R slaves spawned by using slavedaemon.R script and all executed results are returned back to master.

Usage

```
mpi.parSim(n=100, rand.gen=rnorm, rand.arg=NULL, statistic,
           nsim=100, run=1, slaveinfo=FALSE, sim.seq=NULL, simplify=TRUE, comm=1, ...)
```

Arguments

n	sample size.
rand.gen	the random data generating function. See the details section
rand.arg	additional argument list to rand.gen.
statistic	the statistic function to be simulated. See the details section
nsim	the number of simulation carried on a slave which is counted as one slave job.
run	the number of looping. See the details section.
slaveinfo	if TRUE, the numbers of jobs finished by slaves will be displayed.
sim.seq	if reproducing the same simulation is desirable, set it to the integer vector .mpi.parSim generated in previous simulation.
simplify	logical; should the result be simplified to a vector or matrix if possible?
comm	a communicator number
...	optional arguments to statistic

Details

It is assumed that one simulation is carried out as `statistic(rand.gen(n))`, where `rand.gen(n)` can return any values as long as `statistic` can take them. Additional arguments can be passed to `rand.gen` by `rand.arg` as a list. Optional arguments can also be passed to `statistic` by the argument `...`

Each slave job consists of `replicate(nsim, statistic(rand.gen(n)))`, i.e., each job runs `nsim` number of simulation. The returned values are transported from slaves to master.

The total number of simulation (TNS) is calculated as follows. Let `slave.num` be the total number of slaves in a `comm` and it is `mpi.comm.size(comm)-1`. Then `TNS=slave.num*nsim*run` and the total number of slave jobs is `slave.num*run`, where `run` is the number of looping from master

perspective. If `run=1`, each slave will run one slave job. If `run=2`, each slave will run two slaves jobs on average, and so on.

The purpose of using `run` has two folds. It allows a tuneup of slave job size and total number of slave jobs to deal with two different cluster environments. On a cluster of slaves with equal CPU power, `run=1` is often enough. But if `nsim` is too big, one can set `run=2` and the slave job size to be `nsim/2` so that $TNS = \text{slave.num} * (\text{nsim}/2) * (2 * \text{run})$. This may improve R computation efficiency slightly. On a cluster of slaves with different CPU power, one can choose a big value of `run` and a small value of `nsim` so that master can dispatch more jobs to slaves who run faster than others. This will keep all slaves busy so that load balancing is achieved.

The sequence of slaves who deliver results to master are saved into `.mpi.parSim`. It keeps track which part of results done by which slaves. `.mpi.parSim` can be used to reproduce the same simulation result if the same seed is used and the argument `sim.seq` is equal to `.mpi.parSim`.

See the warning section before you use `mpi.parSim`.

Value

The returned values depend on values returned by `replicate` of `statistic(rand.gen(n))` and the total number of simulation (TNS). If `statistic` returns a single value, then the result is a vector of length TNS. If `statistic` returns a vector (list) of length `nrow`, then the result is a matrix of dimension `c(nrow, TNS)`.

Warning

It is assumed that a parallel RNG is used on all slaves. Either the package `rsprng` or `rlecuyer` can be used. To set either of them, use `mpi.setup.rngstream` or `mpi.setup.sprng`. Though `mpi.parSim` works without a parallel RNG, the quality of simulation is not guaranteed.

`mpi.parSim` will automatically transfer `rand.gen` and `statistic` to slaves. However, any functions that `rand.gen` and `statistic` reply on but are not on slaves must be transferred to slaves before using `mpi.parSim`. You can use `mpi.bcast.Robj2slave` for that purpose. The same is applied to required packages or C/Fortran codes. You can use either `mpi.bcast.cmd` or put `required(package)` and/or `dyn.load(so.lib)` into `rand.gen` and `statistic`.

If `simplify` is TRUE, saply style simplication is applied. Otherwise a list of length `slave.num*run` is returned.

Author(s)

Hao Yu

See Also

`mpi.setup.rngstream` `mpi.setup.sprng` `mpi.bcast.cmd` `mpi.bcast.Robj2slave`

`mpi.probe`*MPI_Probe and MPI_Iprobe APIs*

Description

`mpi.probe` uses the source and tag of incoming message to set a status. `mpi.iprobe` does the same except it is a nonblocking call, i.e., returns immediately.

Usage

```
mpi.probe(source, tag, comm = 1, status = 0)
mpi.iprobe(source, tag, comm = 1, status = 0)
```

Arguments

<code>source</code>	the source of incoming message or <code>mpi.any.source()</code> for any source.
<code>tag</code>	a tag number or <code>mpi.any.tag()</code> for any tag.
<code>comm</code>	a communicator number
<code>status</code>	a status number

Details

When `mpi.send` or other nonblocking sends are used to send a message, the receiver may not know the exact length before receiving it. `mpi.probe` is used to probe the incoming message and put some information into a status. Then the exact length can be found by using `mpi.get.count` to such a status. If the wild card `mpi.any.source` or `mpi.any.tag` are used, then one can use `mpi.get.sourcetag` to find the exact source or tag of a sender.

Value

`mpi.probe` returns 1 only after a matching message has been found.

`mpi.iprobe` returns TRUE if there is a message that can be received; FALSE otherwise.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

`mpi.send`, `mpi.recv`, `mpi.get.count`

mpi.realloc	<i>Find and increase the lengths of MPI opaques comm, request, and status</i>
-------------	---

Description

mpi.comm.maxsize, mpi.request.maxsize, and mpi.status.maxsize find the lengths of comm, request, and status arrays respectively.

mpi.realloc.comm, mpi.realloc.request and mpi.realloc.status increase the lengths of comm, request and status arrays to newmaxsize respectively if newmaxsize is bigger than the original maximum size.

Usage

```
mpi.realloc.comm(newmaxsize)
mpi.realloc.request(newmaxsize)
mpi.realloc.status(newmaxsize)
mpi.comm.maxsize()
mpi.request.maxsize()
mpi.status.maxsize()
```

Arguments

newmaxsize an integer.

Details

When **Rmpi** is loaded, Rmpi allocs comm array with size 10, request array with 10,000 and status array with 5,000. They should be enough in most cases. They use less than 150KB system memory. In rare case, one can use mpi.realloc.comm, mpi.realloc.request and mpi.realloc.status to increase them to bigger arrays.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

 mpi.reduce

 MPI_Reduce and MPI_Allreduce APIs

Description

mpi.reduce and mpi.allreduce are global reduction operations. mpi.reduce combines each member's result, using the operation op, and returns the combined value(s) to the member specified by the argument dest. mpi.allreduce is the same as mpi.reduce except that all members receive the combined value(s).

Usage

```
mpi.reduce(x, type=2, op=c("sum", "prod", "max", "min", "maxloc", "minloc"),
          dest = 0, comm = 1)
```

```
mpi.allreduce(x, type=2, op=c("sum", "prod", "max", "min", "maxloc", "minloc"),
             comm = 1)
```

Arguments

x	data to be reduced. Must be the same dim and the same type for all members.
type	1 for integer and 2 for double. Others are not supported.
op	one of "sum", "prod", "max", "min", "maxloc", or "minloc".
dest	rank of destination
comm	a communicator number

Details

It is important that all members in a comm call either all mpi.reduce or all mpi.allreduce even though the master may not be in computation. They must provide exactly the same type and dim vectors to be reduced. If the operation "maxloc" or "minloc" is used, the combined vector is twice as long as the original one since the maximum or minimum ranks are included.

Value

mpi.reduce returns the combined value(s) to the member specified by dest. mpi.allreduce returns the combined values(s) to every member in a comm. The combined value(s) may be the summation, production, maximum, or minimum specified by the argument op. If the op is either "maxloc" or "minloc", then the maximum (minimum) value(s) along the maximum (minimum) rank(s) will be returned.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.gather](#).

mpi.remote.exec *Remote Executions on R slaves*

Description

Remotely execute a command on R slaves spawned by using slavedaemon.R script and return all executed results back to master.

Usage

```
mpi.remote.exec(cmd, ..., comm = 1, ret = TRUE)
```

Arguments

cmd	the command to be executed on R slaves
...	used as arguments to cmd (function command) for passing their (master) values to R slaves, i.e., if 'myfun(x)' will be executed on R slaves with 'x' as master variable, use mpi.remote.exec(cmd=myfun, x).
comm	a communicator number.
ret	return executed results from R slaves if TRUE.

Details

Once R slaves are spawned by [mpi.spawn.Rslaves](#) with the slavedaemon.R script, they are waiting for instructions from master. One can use [mpi.bcast.cmd](#) to send a command to R slaves. However it will not return executed results. Hence `mpi.remote.exec` can be considered an extension to [mpi.bcast.cmd](#).

Value

return executed results from R slaves if the argument `ret` is set to be TRUE. The value could be a data.frame if values (integer or double) from each slave have the same dimension. Otherwise a list is returned.

Warning

`mpi.remote.exec` may have difficult guessing invisible results on R slaves. Use `ret = FALSE` instead.

Author(s)

Hao Yu

See Also[mpi.spawn.Rslaves](#), [mpi.bcast.cmd](#)**Examples**

```
## Not run:
mpi.remote.exec(mpi.comm.rank())
x=5
mpi.remote.exec(rnorm,x)
## End(Not run)
```

 mpi.scatter

MPI_Scatter and MPI_Scatterv APIs

Description

`mpi.scatter` and `mpi.scatterv` are the inverse operations of [mpi.gather](#) and [mpi.gatherv](#) respectively.

Usage

```
mpi.scatter(x, type, rdata, root = 0, comm = 1)
mpi.scatterv(x, counts, type, rdata, root = 0, comm = 1)
```

Arguments

<code>x</code>	data to be scattered.
<code>type</code>	1 for integer, 2 for double, and 3 for character. Others are not supported.
<code>rdata</code>	the receive buffer. Must be the same type as the sender
<code>counts</code>	int vector specifying the block length inside a message to be scattered to other members.
<code>root</code>	rank of the receiver
<code>comm</code>	a communicator number

Details

`mpi.scatter` scatters the message `x` to all members. Each member receives a portion of `x` with `dim` as `length(x)/size` in rank order, where `size` is the total number of members in a `comm`. So the receive buffer can be prepared as either `integer(length(x)/size)` or `double(length(x)/size)`. For `mpi.scatterv`, `counts` counts the portions (different `dims`) of `x` sent to each member. Each member needs to prepare the receive buffer as either `integer(counts[i])` or `double(counts[i])`.

Value

For non-root members, `mpi.scatter` or `scatterv` returns the scattered message and ignores whatever is in `x` (or `scounts`). For the root member, it returns the portion belonging to itself.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.gather](#), [mpi.gatherv](#).

Examples

```
## Not run:
#Need 3 slaves to run properly
#Or run  mpi.spawn.Rslaves(nslaves=3)
  num="123456789abcd"
  scounts<-c(2,3,1,7)
  mpi.bcast.cmd(strnum<-mpi.scatter(integer(1),type=1,rdata=integer(1),root=0))
  strnum<-mpi.scatter(scount,stype=1,rdata=integer(1),root=0)
  mpi.bcast.cmd(ans <- mpi.scatterv(string(1),scount=0,type=3,rdata=string(strnum),root=0))
  mpi.scatterv(as.character(num),scount=scount,stype=3,rdata=string(strnum),root=0)
  mpi.remote.exec(ans)
## End(Not run)
```

mpi.scatter.Robj *Extensions of MPI_SCATTER and MPI_SCATTERV*

Description

`mpi.scatter.Robj` and `mpi.scatter.Robj2slave` are used to scatter a list to all members. They are more efficient than using any parallel apply functions.

Usage

```
mpi.scatter.Robj(obj = NULL, root = 0, comm = 1)
mpi.scatter.Robj2slave(obj, comm = 1)
```

Arguments

<code>obj</code>	a list object to be scattered from the root or master
<code>root</code>	rank of the scatter.
<code>comm</code>	a communicator number.

Details

`mpi.scatter.Robj` is an extension of `mpi.scatter` for scattering a list object from a sender (root) to everyone. `mpi.scatter.Robj2slave` scatters a list to all slaves.

Value

`mpi.scatter.Robj` for non-root members, returns the scattered R object. For the root member, it returns the portion belonging to itself. `mpi.scatter.Robj2slave` returns no value for the master and all slaves get their corresponding components in the list, i.e., the first slave gets the first component in the list.

Author(s)

Hao Yu and Wei Xia

See Also

`mpi.scatter`, `mpi.gather.Robj`,

Examples

```
## Not run:
#assume that there are three slaves running
mpi.bcast.cmd(x<-mpi.scatter.Robj())

xx <- list("master", rnorm(3), letters[2], 1:10)
mpi.scatter.Robj(obj=xx)

mpi.remote.exec(x)
## End(Not run)
```

`mpi.send`

MPI_Send, MPI_Isend, MPI_Recv, and MPI_Irecv APIs

Description

The pair `mpi.send` and `mpi.recv` are two most used blocking calls for point-to-point communications. An int, double or char vector can be transmitted from any source to any destination.

The pair `mpi.isend` and `mpi.irecv` are the same except that they are nonblocking calls.

Blocking and nonblocking calls are interchangeable, e.g., nonblocking sends can be matched with blocking receives, and vice-versa.

Usage

```
mpi.send(x, type, dest, tag, comm = 1)
mpi.isend(x, type, dest, tag, comm = 1, request=0)
mpi.recv(x, type, source, tag, comm = 1, status = 0)
mpi.irecv(x, type, source, tag, comm = 1, request = 0)
```

Arguments

<code>x</code>	data to be sent or received. Must be the same type for source and destination. The receive buffer must be as large as the send buffer.
<code>type</code>	1 for integer, 2 for double, and 3 for character. Others are not supported.
<code>dest</code>	the destination rank. Use <code>mpi.proc.null</code> for a fake destination.
<code>source</code>	the source rank. Use <code>mpi.any.source</code> for any source. Use <code>mpi.proc.null</code> for a fake source.
<code>tag</code>	non-negative integer. Use <code>mpi.any.tag</code> for any tag flag.
<code>comm</code>	a communicator number.
<code>request</code>	a request number.
<code>status</code>	a status number.

Details

The pair `mpi.send` (or `mpi.isend`) and `mpi.recv` (or `mpi.irecv`) must be used together, i.e., if there is a sender, then there must be a receiver. Any mismatch will result a deadlock situation, i.e., programs stop responding. The receive buffer must be large enough to contain an incoming message otherwise programs will be crashed. One can use `mpi.probe` (or `mpi.iprobe`) and `mpi.get.count` to find the length of an incoming message before calling `mpi.recv`. If `mpi.any.source` or `mpi.any.tag` is used in `mpi.recv`, one can use `mpi.get.sourcetag` to find out the source or tag of the received message. To send/receive an R object rather than an int, double or char vector, please use the pair `mpi.send.Robj` and `mpi.recv.Robj`.

Since `mpi.irecv` is a nonblocking call, `x` with enough buffer must be created before using it. Then use nonblocking completion calls such as `mpi.wait` or `mpi.test` to test if `x` contains data from sender.

If multiple nonblocking sends or receives are used, please use request number consecutively from 0. For example, to receive two messages from two slaves, try `mpi.irecv(x,1,source=1,tag=0,comm=1,request=0)` `mpi.irecv(y,1,source=2,tag=0,comm=1,request=1)` Then `mpi.waitany`, `mpi.waitsome` or `mpi.waitall` can be used to complete the operations.

Value

`mpi.send` and `mpi.isend` return no value. `mpi.recv` returns the int, double or char vector sent from `source`. However, `mpi.irecv` returns no value. See details for explanation.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

`mpi.send.Robj`, `mpi.recv.Robj`, `mpi.probe`, `mpi.wait`, `mpi.get.count`, `mpi.get.sourcetag`.

Examples

```
## Not run:
#on a slave
mpi.send(1:10, 1, 0, 0)

#on master
x <- integer(10)
mpi.irecv(x, 1, 1, 0)
x
mpi.wait()
x
## End(Not run)
```

 mpi.send.Robj

Extensions of MPI_Send and MPI_Recv APIs

Description

mpi.send.Robj and mpi.recv.Robj are two extensions of mpi.send and mpi.recv. They are used to transmit a general R object from any source to any destination.

mpi.isend.Robj is a nonblocking version of mpi.send.Robj.

Usage

```
mpi.send.Robj(obj, dest, tag, comm = 1)
mpi.isend.Robj(obj, dest, tag, comm = 1, request=0)
mpi.recv.Robj(source, tag, comm = 1, status = 0)
```

Arguments

obj	an R object. Can be any R object.
dest	the destination rank.
source	the source rank or mpi.any.source() for any source.
tag	non-negative integer or mpi.any.tag() for any tag.
comm	a communicator number.
request	a request number.
status	a status number.

Details

mpi.send.Robj and mpi.isend.Robj use [serialize](#) to encode an R object into a binary char vector. It sends the message to the destination. The receiver decode the message back into an R object by using [unserialize](#).

If mpi.isend.Robj is used, mpi.wait or mpi.test must be used to check the object has been sent.

Value

mpi.send.Robj or mpi.isend.Robj return no value. mpi.recv.Robj returns the the transmitted R object.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

mpi.send, mpi.recv, mpi.wait, serialize, unserialize,

mpi.sendrecv

MPI_Sendrecv and MPI_Sendrecv_replace APIs

Description

mpi.sendrecv and mpi.sendrecv.replace execute blocking send and receive operations. Both of them combine the sending of one message to a destination and the receiving of another message from a source in one call. The source and destination are possibly the same. The send buffer and receive buffer are disjoint for mpi.sendrecv, while the buffers are not disjoint for mpi.sendrecv.replace.

Usage

```
mpi.sendrecv(senddata, sendtype, dest, sendtag, recvdata, recvtype,
source, recvtag, comm = 1, status = 0)
```

```
mpi.sendrecv.replace(x, type, dest, sendtag, source, recvtag,
comm = 1, status = 0)
```

Arguments

x	data to be sent or recieved. Must be the same type for source and destination.
senddata	data to be sent. May have different datatypes and lengths
recvdata	data to be recieved. May have different datatypes and lengths
type	type of the data to be sent or recieved. 1 for integer, 2 for double, and 3 for character. Others are not supported.
sendtype	type of the data to be sent. 1 for integer, 2 for double, and 3 for character. Others are not supported.
recvtype	type of the data to be recieved. 1 for integer, 2 for double, and 3 for character. Others are not supported.

dest	the destination rank. Use <code>mpi.proc.null</code> for a fake destination.
source	the source rank. Use <code>mpi.any.source</code> for any source. Use <code>mpi.proc.null</code> for a fake source.
sendtag	non-negative integer. Use <code>mpi.any.tag</code> for any tag flag.
recvtag	non-negative integer. Use <code>mpi.any.tag</code> for any tag flag.
comm	a communicator number.
status	a status number.

Details

The receive buffer must be large enough to contain an incoming message otherwise programs will be crashed. There is compatibility between send-receive and normal sends and receives. A message sent by a send-receive can be received by a regular receive and a send-receive can receive a message sent by a regular send.

Value

Returns the int, double or char vector sent from the send buffers.

Author(s)

Kris Chen

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

[mpi.send.Robj](#), [mpi.recv.Robj](#), [mpi.probe](#), [mpi.get.sourcetag](#).

Examples

```
mpi.sendrecv(as.integer(11:20), 1, 0, 33, integer(10), 1, 0, 33, comm=0)
mpi.sendrecv.replace(seq(1, 2, by=0.1), 2, 0, 99, 0, 99, comm=0)
```

`mpi.setup.sprng` *Setup parallel RNG on all slaves*

Description

`mpi.setup.sprng` setups SPRNG (**rsprng**) on all slaves. `mpi.setup.rngstream` setups RNGstream (**rlecuyer**) on all slaves.

Usage

```
mpi.setup.sprng(seed=runif(1, 1, 2^31-1), kindprng="default", para=0, comm=1)
mpi.setup.rngstream(seed=c(runif(3, 0, 2^32-210), runif(3, 0, 2^32-22854)),
                    comm = 1)
```

Arguments

seed	an integer or a vector of 6 integers of random number seed(s).
kindprng	a character string of the desired kind of parallel random number generator.
para	additional parameters for the parallel random number generators. If para is 0, default parameters for each PRNG are used. When invalid parameter is given, a warning is issued and the default parameter is used.
comm	a comm number.

Details

mpi.setup.sprng and mpi.setup.rngstream can be run only on master node. Please use one and only one of them on one session. According to SPRNG specification, one can only run mpi.setup.sprng once before using any RNG on slaves. Otherwise independence of streams on slaves are not guaranteed. If several simulations with different seeds are desirable on one session, mpi.setup.rngstream is preferred.

Value

If setup fails, an error message will be returned. It is most likely that the **rsprng** or **rlcuyer** is not installed properly on all slaves. mpi.setup.sprng and mpi.setup.rngstream save their seeds as .Sprng.seed and .Rngstream.seed respectively.

Author(s)

Hao Yu

mpi.spawn.Rslaves *Spawn and Close R Slaves*

Description

mpi.spawn.Rslaves spawns R slaves to those hosts automatically chosen by MPI or specific hosts assigned by the argument `hosts`. Those R slaves are running in R BATCH mode with a specific Rscript file. The default Rscript file "slavedaemon.R" provides interactive R slave environments.

mpi.close.Rslaves shuts down R slaves spawned by mpi.spawn.Rslaves.

tailslave.log view (from tail) R slave log files (assuming they are all in one working directory).

Usage

```

mpi.spawn.Rslaves(Rscript=system.file("slavedaemon.R", package="Rmpi"),
                  nslaves=mpi.universe.size(), root = 0, intercomm = 2,
                  comm = 1, hosts = NULL, needlog = TRUE, mapdrive=TRUE)

mpi.close.Rslaves(dellog = TRUE, comm = 1)
tailslave.log(nlines = 3, comm = 1)

```

Arguments

Rscript	an R script file used to run R in BATCH mode.
nslaves	number of slaves to be spawned.
root	the rank number of the member who spawns R slaves.
intercomm	an intercommunicator number
comm	a communicator number merged from an intercomm.
hosts	NULL or LAM node numbers to specify where R slaves to be spawned.
needlog	a logical. If TRUE, R BATCH outputs will be saved in log files. If FALSE, the outputs will send to /dev/null.
mapdrive	a logical. If TRUE and master's working dir is on a network, mapping network drive is attempted on remote nodes under windows platform.
dellog	a logical specifying if R slave's log files are deleted or not.
nlines	number of lines to view from tail in R slave's log files.

Details

The R slaves that `mpi.spawn.Rslaves` spawns are really running a shell program which can be found in `system.file("Rslaves.sh", package="Rmpi")` which takes a `Rscript` file as one of its arguments. Other arguments are used to see if a log file (R output) is needed and how to name it. The master process id and the comm number, along with host names where R slaves are running are used to name these log files.

Once R slaves are successfully spawned, the mergers from an intercomm (default 'intercomm = 2') to a comm (default 'comm = 1') are automatically done on master and slaves (should be done if the default `Rscript` is replaced). If additional sets of R slaves are needed, please use 'comm = 3', 'comm = 4', etc to spawn them. At most a comm number up to 10 can be used. Notice that the default comm number for R slaves (using `slavedaemon.R`) is always 1 which is saved as `.comm`.

To spawn R slaves to specific hosts, please use the argument `hosts` with a list of those node numbers (an integer vector). Total node numbers along their host names can be found by using [lamhosts](#). Notice that this is LAM-MPI specific.

Value

`mpi.spawn.Rslaves` prints to stdio how many slaves are successfully spawned and where they are running.

`mpi.close.Rslaves` return 1 if success and 0 otherwise.

`tailslave.log` returns last lines of R slave's log files.

Author(s)

Hao Yu

See Also[mpi.comm.spawn](#), [lamhosts](#).**Examples**

```
## Not run:
mpi.spawn.Rslaves(nslaves=2)
tailslave.log()
mpi.remote.exec(rnorm(10))
mpi.close.Rslaves()
## End(Not run)
```

`mpi.universe.size` *MPI_Universe_size API*

Description

`mpi.universe.size` returns the total number of CPUs available in a cluster. Some MPI implementations may not have this MPI call available.

Usage

```
mpi.universe.size()
```

Arguments

None.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

`mpi.wait`*Nonblocking completion operations*

Description

`mpi.cancel` cancels a nonblocking send or receive request.

`mpi.test.cancelled` tests if `mpi.cancel` cancels or not.

`wait`, `waitall`, `waitany`, and `waitsome` are used to complete nonblocking send or receive requests. They are not local.

`test`, `testall`, `testany`, and `testsome` are used to complete nonblocking send and receive requests. They are local.

Usage

```
mpi.cancel(request)
mpi.test.cancelled(status=0)
mpi.test(request, status=0)
mpi.testall(count)
mpi.testany(count, status=0)
mpi.testsome(count)
mpi.wait(request, status=0)
mpi.waitall(count)
mpi.waitany(count, status=0)
mpi.waitsome(count)
```

Arguments

<code>count</code>	total number of nonblocking operations.
<code>request</code>	a request number.
<code>status</code>	a status number.

Details

`mpi.wait` and `mpi.test` are used to complete a nonblocking send and receive request: use the same request number by `mpi.isend` or `mpi.irecv`. Once completed, the associated request is set to `MPI_REQUEST_NULL` and status contains information such as source, tag, and length of message.

If multiple nonblocking sends or receives are initiated, the following calls are more efficient. Make sure that request numbers are used consecutively as `request=0`, `request=1`, `request=2`, etc. In this way, the following calls can find request information in system memory.

`mpi.waitany` and `mpi.testany` are used to complete one out of several requests.

`mpi.waitall` and `mpi.testall` are used to complete all requests.

`mpi.waitsome` and `mpi.testsome` are used to complete all enabled requests.

Value

`mpi.cancel` returns no value.

`mpi.test.cancelled` returns TRUE if a nonblocking call is cancelled; FALSE otherwise.

`mpi.wait` returns no value. Instead status contains information that can be retrieved by `mpi.get.count` and `mpi.get.sourcetag`.

`mpi.test` returns TRUE if a request is complete; FALSE otherwise. If TRUE, it is the same as `mpi.wait`.

`mpi.waitany` returns which request (index) has been completed. In addition, status contains information that can be retrieved by `mpi.get.count` and `mpi.get.sourcetag`.

`mpi.testany` returns a list: index— request index; flag—TRUE if a request is complete; FALSE otherwise (index is no use in this case). If flag is TRUE, it is the same as `mpi.waitany`.

`mpi.waitall` returns no value. Instead statuses 0, 1, ..., count-1 contain corresponding information that can be retrieved by `mpi.get.count` and `mpi.get.sourcetag`.

`mpi.testall` returns TRUE if all requests are complete; FALSE otherwise. If TRUE, it is the same as `mpi.waitall`.

`mpi.waitsome` returns a list: count— number of requests that have been completed; indices— an integer vector of size \$count of those completed request numbers (in 0, 1, ..., count-1). In addition, statuses 0, 1, ..., \$count-1 contain corresponding information that can be retrieved by `mpi.get.count` and `mpi.get.sourcetag`.

`mpi.testsome` is the same as `mpi.waitsome` except that \$count may be 0 and in this case \$indices is no use.

Author(s)

Hao Yu

References

<http://www.lam-mpi.org/>, <http://www-unix.mcs.anl.gov/mpi/www/www3/>

See Also

`mpi.isend`, `mpi.irecv`, `mpi.get.count`, `mpi.get.sourcetag`.

Index

*Topic **distribution**

- `mpi.init.sprng`, 32
- `mpi.setup.sprng`, 46

*Topic **interface**

- `mpi.abort`, 3
- `mpi.barrier`, 7
- `mpi.bcast`, 8
- `mpi.cart.coords`, 11
- `mpi.cart.create`, 12
- `mpi.cart.get`, 13
- `mpi.cart.rank`, 14
- `mpi.cart.shift`, 15
- `mpi.cartdim.get`, 16
- `mpi.comm.disconnect`, 17
- `mpi.comm.free`, 18
- `mpi.comm.get.parent`, 19
- `mpi.comm.set.errhandler`, 20
- `mpi.comm.size`, 20
- `mpi.comm.spawn`, 21
- `mpi.dims.create`, 22
- `mpi.finalize`, 24
- `mpi.gather`, 25
- `mpi.gather.Robj`, 26
- `mpi.get.count`, 27
- `mpi.get.processor.name`, 28
- `mpi.info.create`, 31
- `mpi.init.sprng`, 32
- `mpi.intercomm.merge`, 33
- `mpi.probe`, 36
- `mpi.realloc`, 37
- `mpi.reduce`, 38
- `mpi.scatter`, 40
- `mpi.send`, 42
- `mpi.sendrecv`, 45
- `mpi.setup.sprng`, 46
- `mpi.universe.size`, 49
- `mpi.wait`, 50

*Topic **utilities**

- `bin.nchar`, 1

- `lamhosts`, 2
- `mpi.any.source`, 4
- `mpi.apply`, 5
- `mpi.applyLB`, 6
- `mpi.bcast.cmd`, 9
- `mpi.bcast.Robj`, 10
- `mpi.exit`, 23
- `mpi.get.sourcetag`, 29
- `mpi.iapplyLB`, 30
- `mpi.parSim`, 34
- `mpi.remote.exec`, 39
- `mpi.scatter.Robj`, 41
- `mpi.send.Robj`, 44
- `mpi.spawn.Rslaves`, 47

- `bin.nchar`, 1

- `deparse`, 9

- `free.sprng`, 32

- `init.sprng`, 33

- `lamhosts`, 2, 48, 49

- `mpi.abort`, 3
- `mpi.allgather` (`mpi.gather`), 25
- `mpi.allgather.Robj`
(`mpi.gather.Robj`), 26
- `mpi.allgatherv`, 27
- `mpi.allgatherv` (`mpi.gather`), 25
- `mpi.allreduce` (`mpi.reduce`), 38
- `mpi.any.source`, 4, 29, 43
- `mpi.any.tag`, 29, 43
- `mpi.any.tag` (`mpi.any.source`), 4
- `mpi.apply`, 5, 7
- `mpi.applyLB`, 6
- `mpi.barrier`, 7
- `mpi.bcast`, 8, 9, 10
- `mpi.bcast.cmd`, 8, 9, 9, 35, 39, 40
- `mpi.bcast.Robj`, 8, 9, 10

- mpi.bcast.Robj2slave, 8, 9, 35
- mpi.bcast.Robj2slave
 - (*mpi.bcast.Robj*), 10
- mpi.cancel(*mpi.wait*), 50
- mpi.cart.coords, 11, 14
- mpi.cart.create, 12, 13, 15, 23
- mpi.cart.get, 13, 16
- mpi.cart.rank, 11, 14
- mpi.cart.shift, 15
- mpi.cartdim.get, 16
- mpi.close.Rslaves
 - (*mpi.spawn.Rslaves*), 47
- mpi.comm.disconnect, 17, 18
- mpi.comm.dup(*mpi.comm.size*), 20
- mpi.comm.free, 17, 18
- mpi.comm.get.parent, 19, 21, 22, 33
- mpi.comm.is.null(*bin.nchar*), 1
- mpi.comm.maxsize(*mpi.realloc*), 37
- mpi.comm.rank(*mpi.comm.size*), 20
- mpi.comm.remote.size
 - (*mpi.comm.get.parent*), 19
- mpi.comm.set.errhandler, 20
- mpi.comm.size, 18, 20
- mpi.comm.spawn, 21, 49
- mpi.comm.test.inter, 33, 34
- mpi.comm.test.inter
 - (*mpi.comm.get.parent*), 19
- mpi.dims.create, 22
- mpi.exit, 23, 24
- mpi.finalize, 4, 17, 23, 24, 24
- mpi.gather, 25, 27, 39–41
- mpi.gather.Robj, 26, 42
- mpi.gatherv, 40, 41
- mpi.gatherv(*mpi.gather*), 25
- mpi.get.count, 27, 29, 36, 43, 51
- mpi.get.processor.name, 28
- mpi.get.sourcetag, 28, 29, 29, 36, 43, 46, 51
- mpi.hostinfo(*lamhosts*), 2
- mpi.iapply, 31
- mpi.iapply(*mpi.apply*), 5
- mpi.iapplyLB, 30
- mpi.info.create, 31
- mpi.info.free(*mpi.info.create*), 31
- mpi.info.get(*mpi.info.create*), 31
- mpi.info.set(*mpi.info.create*), 31
- mpi.init.sprng, 32
- mpi.intercomm.merge, 17–19, 21, 22, 33
- mpi.iparApply(*mpi.iapplyLB*), 30
- mpi.iparCapply(*mpi.iapplyLB*), 30
- mpi.iparLapply(*mpi.iapplyLB*), 30
- mpi.iparRapply(*mpi.iapplyLB*), 30
- mpi.iparReplicate(*mpi.iapplyLB*), 30
- mpi.iparSapply(*mpi.iapplyLB*), 30
- mpi.iprobe, 43
- mpi.iprobe(*mpi.probe*), 36
- mpi.irecv, 51
- mpi.irecv(*mpi.send*), 42
- mpi.is.master(*lamhosts*), 2
- mpi.isend, 51
- mpi.isend(*mpi.send*), 42
- mpi.isend.Robj(*mpi.send.Robj*), 44
- mpi.parallel.sim(*mpi.parSim*), 34
- mpi.parApply(*mpi.applyLB*), 6
- mpi.parCapply(*mpi.applyLB*), 6
- mpi.parLapply(*mpi.applyLB*), 6
- mpi.parRapply(*mpi.applyLB*), 6
- mpi.parReplicate(*mpi.applyLB*), 6
- mpi.parSapply(*mpi.applyLB*), 6
- mpi.parSim, 34
- mpi.probe, 4, 28, 29, 36, 43, 46
- mpi.proc.null, 15
- mpi.proc.null(*mpi.any.source*), 4
- mpi.quit(*mpi.exit*), 23
- mpi.realloc, 37
- mpi.realloc.comm(*mpi.realloc*), 37
- mpi.realloc.request
 - (*mpi.realloc*), 37
- mpi.realloc.status(*mpi.realloc*), 37
- mpi.recv, 4, 27–29, 36, 45
- mpi.recv(*mpi.send*), 42
- mpi.recv.Robj, 10, 43, 46
- mpi.recv.Robj(*mpi.send.Robj*), 44
- mpi.reduce, 38
- mpi.remote.exec, 9, 10, 39
- mpi.request.maxsize
 - (*mpi.realloc*), 37
- mpi.scatter, 26, 40, 42
- mpi.scatter.Robj, 41
- mpi.scatter.Robj2slave
 - (*mpi.scatter.Robj*), 41
- mpi.scatterv, 26
- mpi.scatterv(*mpi.scatter*), 40

`mpi.send`, 4, 28, 29, 36, 42, 45
`mpi.send.Robj`, 10, 43, 44, 46
`mpi.sendrecv`, 45
`mpi.setup.rngstream`, 35
`mpi.setup.rngstream`
 (`mpi.setup.sprng`), 46
`mpi.setup.sprng`, 35, 46
`mpi.spawn.Rslaves`, 2, 3, 32, 33, 39, 40,
 47
`mpi.status.maxsize` (`mpi.realloc`),
 37
`mpi.test`, 43
`mpi.test` (`mpi.wait`), 50
`mpi.testall` (`mpi.wait`), 50
`mpi.testany` (`mpi.wait`), 50
`mpi.testsome` (`mpi.wait`), 50
`mpi.universe.size`, 49
`mpi.wait`, 43, 45, 50
`mpi.waitall` (`mpi.wait`), 50
`mpi.waitany` (`mpi.wait`), 50
`mpi.waitsome` (`mpi.wait`), 50
`mpichhosts` (`lamhosts`), 2

parse, 9

replicate, 35

serialize, 44, 45
`slave.hostinfo` (`lamhosts`), 2
`string` (`bin.nchar`), 1

`tailslave.log`
 (`mpi.spawn.Rslaves`), 47

unserialize, 44, 45